

Coherent PDF Library (libcpdf)

Developer's Manual

Version 2.2 (January 2017)



Coherent Graphics Ltd

Instructions

This is the manual for the C API to the Coherent PDF Command Line Tools.

It consists of the ordinary manual for the command line tools, followed by the C API, structured chapter-by-chapter the same as the chapters of the command line tools manual.

The canonical API to the Coherent PDF Command Line tools is the command line. You should experiment with little pieces of your proposed program at the command line first, before trying to write it as a C program: you will find errors much more quickly like this.

Coherent PDF Command Line Toolkit

User Manual
Version 2.4 (? 2020)



Coherent Graphics Ltd

For bug reports, feature requests and comments, email
contact@coherentgraphics.co.uk

©2020 Coherent Graphics Limited. All rights reserved. ISBN 978-0957671140

Adobe, Acrobat, Adobe PDF, Adobe Reader and PostScript are registered trademarks of Adobe Systems Incorporated. Windows, Powerpoint and Excel are registered trademarks of Microsoft Corporation.

Contents

1	Basic Usage	1
1.1	Documentation	1
1.2	Input and Output Files	1
1.3	Input Ranges	2
1.4	Working with Encrypted Documents	3
1.5	Standard Input and Standard Output	4
1.6	Doing Several Things at Once with AND	4
1.7	Units	5
1.8	Setting the Producer and Creator	5
1.9	PDF Version Numbers	6
1.10	File IDs	6
1.11	Linearization	6
1.12	Object Streams	7
1.13	Malformed Files	7
1.14	Error Handling	9
1.15	Control Files	9
1.16	String Arguments	9
1.17	Text Encodings	10
1.18	Font Embedding	10
1.19	Creating a new PDF	10
2	Merging and Splitting	11
2.1	Merging	11
2.2	Splitting	12
2.3	Splitting on Bookmarks	12
2.4	Encrypting with Split and Split Bookmarks	13
3	Pages	15
3.1	Page Sizes	16
3.2	Scale Pages	16
3.3	Shift Page Contents	17
3.4	Rotating Pages	17
3.5	Flipping Pages	18
3.6	Boxes and Cropping	18
3.7	Showing Boxes and Printer's Marks	19

4	Encryption and Decryption	21
4.1	Introduction	21
4.2	Encrypting a Document	22
4.3	Decrypting a Document	22
5	Compression	23
5.1	Decompressing a Document	23
5.2	Compressing a Document	23
5.3	Squeezing a Document	24
6	Bookmarks	25
6.1	List Bookmarks	25
6.1.1	Destinations	26
6.2	Remove Bookmarks	27
6.3	Add Bookmarks	27
6.4	Opening bookmarks	27
7	Presentations	29
8	Watermarks and Stamps	31
8.1	Add a Watermark or Logo	32
8.2	Stamp Text, Dates and Times.	32
8.2.1	Page Numbers	33
8.2.2	Date and Time Formats	33
8.2.3	Bates Numbers	33
8.2.4	Position	34
8.2.5	Font and Size	34
8.2.6	Colors	35
8.2.7	Outline Text	36
8.2.8	Multi-line Text	36
8.2.9	Special Characters	36
8.3	Stamping Graphics	37
9	Multipage Facilities	39
9.1	Two-up	39
9.2	Inserting Blank Pages	39
10	Annotations	41
10.1	List Annotations	41
10.2	Copy Annotations	41
10.3	Remove Annotations	42
11	Document Information and Metadata	43
11.1	Listing Fonts	44
11.2	Reading Document Information	44
11.3	Setting Document Information	45
11.4	XMP Metadata	46
11.5	Upon Opening a Document	47

11.5.1	Page Layout	47
11.5.2	Page Mode	47
11.5.3	Display Options	48
11.6	Page Labels	48
12	File Attachments	51
12.1	Adding Attachments	51
12.2	Listing Attachments	51
12.3	Removing Attachments	52
12.4	Dumping Attachments to File	52
13	Working with Images	53
13.1	Detecting Low-resolution Images	53
13.2	Removing an Image	53
14	Fonts	55
14.1	Listing Fonts	55
14.2	Copying Fonts	56
14.3	Removing Fonts	56
14.4	Missing Fonts	56
15	Miscellaneous	59
15.1	Draft Documents	59
15.2	Blackening Text, Lines and Fills	60
15.3	Hairline Removal	60
15.4	Garbage Collection	61
15.5	Change PDF Version Number	61
15.6	Copy ID	61
15.7	Remove ID	61
15.8	List Spot Colours	62
15.9	Removing Dictionary Entries	62
15.10	Removing Clipping	62
A	Dates	63
A.1	PDF Date Format	63
A.2	XMP Metadata Date Format	64

Typographical Conventions

Command lines to be typed are shown in typewriter font in a box. For example:

```
cpdf in.pdf -o out.pdf
```

When describing the general form of a command, rather than a particular example, square brackets `[]` are used to enclose optional parts, and angled braces `<>` to enclose general descriptions which may be substituted for particular instances. For example,

```
cpdf <operation> in.pdf [<range>] -o out.pdf
```

describes a command line which requires an operation and, optionally, a range. An exception is that we use `in.pdf` and `out.pdf` instead of `<input file>` and `<output file>` to reduce verbosity. Under Microsoft Windows, type `cpdf.exe` instead of `cpdf`.

Chapter 1

Basic Usage

-help	--help	-version
-o	-idir <directory>	-recrypt
-stdout	-stdin	-stdin-user <password>
-stdin-owner <password>	-producer <text>	-creator <text>
-change-id	-l	-cpdfin <filename>
-keep-l	-no-preserve-objstm	-create-objstm
-control <filename>	-args <filename>	-utf8
-stripped	-raw	-no-embed-font
-create-pdf	-create-pdf-pages	-create-pdf-papersize
-gs	-gs-malformed	-gs-force-malformed
-gs-quiet	-error-on-malformed	

The Coherent PDF tools provide a wide range of facilities for modifying PDF files created by other means. There is a single command-line program `cpdf` (`cpdf.exe` under Microsoft Windows). The rest of this manual describes the options that may be given to this program.

1.1 Documentation

The operation `-help` / `--help` prints each operation and option together with a short description. The operation `-version` prints the `cpdf` version string.

1.2 Input and Output Files

The typical pattern for usage is

```
cpdf [<operation>] <input file(s)> -o <output file>
```

and the simplest concrete example, assuming the existence of a file `in.pdf` is:

```
cpdf in.pdf -o out.pdf
```

which copies `in.pdf` to `out.pdf`. The input and output may be the same file. Of course, we should like to do more interesting things to the PDF file than that!

Files on the command line are distinguished from other input by their containing a period. If an input file does not contain a period, it should be preceded by `-i`. For example:

```
cpdf -i in -o out.pdf
```

A whole directory of files may be added (where a command supports multiple files) by using the `-idir` option:

```
cpdf -merge -idir myfiles -o out.pdf
```

The files in the directory `myfiles` are considered in alphabetical order. They must all be PDF files. If the names of the files are numeric, leading zeroes will be required for the order to be correct (e.g. `001.pdf`, `002.pdf` etc).

1.3 Input Ranges

An *input range* may be specified after each input file. This is treated differently by each operation. For instance

```
cpdf in.pdf 2-5 out.pdf
```

extracts pages two, three, four and five from `in.pdf`, writing the result to `out.pdf`, assuming that `in.pdf` contains at least five pages. Here are the rules for building input ranges:

- A dash (`-`) defines ranges, e.g. `1-5` or `6-3`.
- A comma (`,`) allows one to specify several ranges, e.g. `1-2, 4-5`.
- The word `end` represents the last page number.
- The words `odd` and `even` can be used in place of or at the end of a page range to restrict to just the odd or even pages.
- The words `portrait` and `landscape` can be used in place of or at the end of a page range to restrict to just those pages which are portrait or landscape. Note that the meaning of “portrait” and “landscape” does not take account of any viewing rotation in place (use `-upright` first, if required). A page with equal width and height is considered neither portrait nor landscape.

- The word `reverse` is the same as `end-1`.
- The word `all` is the same as `1-end`.
- A range must contain no spaces.
- A tilde (`~`) defines a page number counting from the end of the document rather than the beginning. Page `~1` is the last page, `~2` the penultimate page etc.

For example:

```
cpdf in.pdf 1,2,7-end -o out.pdf
```

Remove pages three, four, five and six from a document.

```
cpdf in.pdf 1-16odd -o out.pdf
```

Extract the odd pages 1,3,...,13,15.

```
cpdf in.pdf landscape -rotate 90 -o out.pdf
```

Rotate all landscape pages by ninety degrees.

```
cpdf in.pdf 1,all -o out.pdf
```

Duplicate the front page of a document, perhaps as a fax cover sheet.

```
cpdf in.pdf ~3-~1 -o out.pdf
```

Extract the last three pages of a document, in order.

1.4 Working with Encrypted Documents

In order to perform many operations, encrypted input PDF files must be decrypted. Some require the owner password, some either the user or owner passwords. Either password is supplied by writing `user=<password>` or `owner=<password>` following each input file requiring it (before or after any range). The document will *not* be re-encrypted upon writing. For example:

```
cpdf in.pdf user=charles -info
cpdf in.pdf owner=fred reverse -o out.pdf
```

To re-encrypt the file with its existing encryption upon writing, which is required if only the user password was supplied, but allowed in any case, add the `-reencrypt` option:

```
cpdf in.pdf user=fred reverse -reencrypt -o out.pdf
```

The password required (owner or user) depends upon the operation being performed. Separate facilities are provided to decrypt and encrypt files (See Section 4).

1.5 Standard Input and Standard Output

Thus far, we have assumed that the input PDF will be read from a file on disk, and the output written similarly. Often it's useful to be able to read input from `stdin` (Standard Input) or write output to `stdout` (Standard Output) instead. The typical use is to join several programs together into a *pipe*, passing data from one to the next without the use of intermediate files. Use `-stdin` to read from standard input, and `-stdout` to write to standard input, either to pipe data between multiple programs, or multiple invocations of the same program. For example, this sequence of commands (all typed on one line)

```
cpdf in.pdf reverse -stdout |  
cpdf -stdin 1-5 -stdout |  
cpdf -stdin reverse -o out.pdf
```

extracts the last five pages of `in.pdf` in the correct order, writing them to `out.pdf`. It does this by reversing the input, taking the first five pages and then reversing the result.

To supply passwords for a file from `-stdin`, use `-stdin-owner <password>` and/or `-stdin-user <password>`.

Using `-stdout` on the final command in the pipeline to output the PDF to screen is not recommended, since PDF files often contain compressed sections which are not screen-readable.

Several `cpdf` operations write to standard output by default (for example, listing fonts). A useful feature of the command line (not specific to `cpdf`) is the ability to redirect this output to a file. This is achieved with the `>` operator:

```
cpdf -info in.pdf > file.txt
```

Use the `-info` operation (See Section 11.2), redirecting the output to `file.txt`.

1.6 Doing Several Things at Once with AND

The keyword `AND` can be used to string together several commands in one. The advantage compared with using pipes is that the file need not be repeatedly parsed and written out, saving time.

To use `AND`, simply leave off the output specifier (e.g. `-o`) of one command, and the input specifier (e.g. filename) of the next. For instance:

```
cpdf -merge in.pdf in2.pdf AND -add-text "Label"  
AND -merge in3.pdf -o out.pdf
```

Merge `in.pdf` and `in2.pdf` together, add text to both pages, append `in3.pdf` and write to `out.pdf`.

To specify the range for each section, use `-range`:

```
cpdf -merge in.pdf in2.pdf AND -range 2-4 -add-text "Label"
      AND -merge in3.pdf -o out.pdf
```

1.7 Units

When measurements are given to `cpdf`, they are in points (1 point = 1/72 inch). They may optionally be followed by some letters to change the measurement. The following are supported:

<code>pt</code>	Points (72 points per inch). The default.
<code>cm</code>	Centimeters
<code>mm</code>	Millimeters
<code>in</code>	Inches

For example, one may write `14mm` or `21.6in`. In addition, the following letters stand, in some operations (`-scale-page`, `-scale-to-fit`, `-scale-contents`, `-shift`, `-mediabox`, `-crop`) for various page dimensions:

<code>PW</code>	Page width
<code>PH</code>	Page height
<code>PMINX</code>	Page minimum x coordinate
<code>PMINY</code>	Page minimum y coordinate
<code>PMAXX</code>	Page maximum x coordinate
<code>PMAXY</code>	Page maximum y coordinate
<code>CW</code>	Crop box width
<code>CH</code>	Crop box height
<code>CMINX</code>	Crop box minimum x coordinate
<code>CMINY</code>	Crop box minimum y coordinate
<code>CMAXX</code>	Crop box maximum x coordinate
<code>CMAXY</code>	Crop box maximum y coordinate

For example, we may write `PMINX PMINY` to stand for the coordinate of the lower left corner of the page.

Simple arithmetic may be performed using the words `add`, `sub`, `mul` and `div` to stand for addition, subtraction, multiplication and division. For example, one may write `14in sub 30pt` or `PMINX mul 2`

1.8 Setting the Producer and Creator

The `-producer` and `-creator` options may be added to any `cpdf` command line to set the producer and/or creator of the PDF file. If the file was converted from another format, the *creator* is the program producing the original, the *producer* the program converting it to PDF.


```
cpdf -merge in.pdf in2.pdf -producer MyMerger -o out.pdf
```

Merge `in.pdf` and `in2.pdf`, setting the producer to `MyMerger` and writing the output to `out.pdf`.

1.9 PDF Version Numbers

When an operation which uses a part of the PDF standard which was introduced in a later version than that of the input file, the PDF version in the output file is set to the later version (most PDF viewers will try to load any PDF file, even if it is marked with a later version number). However, this automatic version changing may be suppressed with the `-keep-version` option. If you wish to manually alter the PDF version of a file, use the `-set-version` operation described in Section 15.5.

1.10 File IDs

PDF files contain an ID (consisting of two parts), used by some workflow systems to uniquely identify a file. To change the ID, behavior, use the `-change-id` operation. This will create a new ID for the output file.

```
cpdf -change-id in.pdf -o out.pdf
```

Write `in.pdf` to `out.pdf`, changing the ID.

1.11 Linearization

Linearized PDF is a version of the PDF format in which the data is held in a special manner to allow content to be fetched only when needed. This means viewing a multipage PDF over a slow connection is more responsive. By default, `cpdf` does not linearize output files. To make it do so, add the `-l` option to the command line, in addition to any other command being used. For example:

```
cpdf -l in.pdf -o out.pdf
```

Linearize the file `in.pdf`, writing to `out.pdf`.

This requires the existence of the external program `cpdfwin` which is provided with commercial versions of `cpdf`. This must be installed as described in the installation documentation provided with your copy of `cpdf`. If you are unable to install `cpdfwin`, you must use `-cpdfwin` to let `cpdf` know where to find it:

```
cpdf.exe -cpdflin "C:\\cpdf\lin.exe" -l in.pdf -o out.pdf
```

Linearize the file `in.pdf`, writing to `out.pdf`.

In extremis, you may place `cpdf\lin` and its resources in the current working directory, though this is not recommended. For further help, refer to the installation instructions for your copy of `cpdf`.

To keep the existing linearization status of a file (produce linearized output if the input is linearized and the reverse), use `-keep-l` instead of `-l`.

1.12 Object Streams

PDF 1.5 introduced a new mechanism for storing objects to save space: object streams. by default, `cpdf` will preserve object streams in input files, creating no more. To prevent the retention of existing object streams, use `-no-preserve-objstm`:

```
cpdf -no-preserve-objstm in.pdf -o out.pdf
```

Write the file `in.pdf` to `out.pdf`, removing any object streams.

To create new object streams if none exist, or augment the existing ones, use `-create-objstm`:

```
cpdf -create-objstm in.pdf -o out.pdf
```

Write the file `in.pdf` to `out.pdf`, preserving any existing object streams, and creating any new ones for new objects which have been added.

To create wholly new object streams, use both options together:

```
cpdf -create-objstm -no-preserve-objstm in.pdf -o out.pdf
```

Write the file `in.pdf` to `out.pdf` with wholly new object streams.

Files written with object streams will be set to PDF 1.5 or higher, unless `-keep-version` is used (see above).

1.13 Malformed Files

There are many malformed PDF files in existence, including many produced by otherwise-reputable applications. `cpdf` attempts to correct these problems silently.

Grossly malformed files will be reconstructed. The reconstruction progress is shown on `stderr` (Standard Error):

```
$cpdf in.pdf -o out.pdf
couldn't lex object number
Attempting to reconstruct the malformed pdf in.pdf...
Read 5530 objects
Malformed PDF reconstruction succeeded!
```

If `cpdf` cannot reconstruct a malformed file, it is able to use the `gs` program to try to reconstruct the program, if you have it installed. For example, if `gs` is installed and in your path, we might try:

```
cpdf -gs gs -gs-malformed in.pdf -o out.pdf
```

To suppress the output of `gs` use the `-gs-quiet` option.

If the malformity lies inside an individual page of the PDF, rather than in its gross structure, `cpdf` may appear to succeed in reconstruction, only to fail when processing a page (e.g when adding text). To force the use of `gs` to pre-process such files so `cpdf` cannot fail on them, use `-gs-malformed-force`:

```
cpdf in.pdf -gs gs -gs-malformed-force -o out.pdf [-gs-quiet]
```

The command line for `-gs-malformed-force` must be of *precisely* this form. Sometimes, on the other hand, we might wish `cpdf` to fail immediately on any malformed file, rather than try its own reconstruction process. The option `-error-on-malformed` achieves this.

Sometimes files can be technically well-formed but use inefficient PDF constructs. If you are sure the input files you are using are impeccably formed, the `-fast` option added to the command line (or, if using `AND`, to each section of the command line). This will use certain shortcuts which speed up processing, but would fail on badly-produced files. The `-fast` option may be used with:

```
Chapter 3
-rotate-contents -upright -vflip -hflip
-shift -scale-page -scale-to-fit -scale-contents
-show-boxes -hard-box -trim-marks
```

```
Chapter 8
-add-text -add-rectangle
-stamp-on -stamp-under -combine-pages
```

```
Chapter 9
-twoup -twoup-stack
```

If problems occur, refrain from using `-fast`.

1.14 Error Handling

When `cpdf` encounters an error, it exits with code 2. An error message is displayed on `stderr` (Standard Error). In normal usage, this means it's displayed on the screen. When a bad or inappropriate password is given, the exit code is 1.

1.15 Control Files

```
cpdf -control <filename>  
cpdf -args <filename>
```

Some operating systems have a limit on the length of a command line. To circumvent this, or simply for reasons of flexibility, a control file may be specified from which arguments are drawn. This file does not support the full syntax of the command line. Commands are separated by whitespace, quotation marks may be used if an argument contains a space, and the sequence `\` may be used to introduce a genuine quotation mark in such an argument.

Several `-control` arguments may be specified, and may be mixed in with conventional command-line arguments. The commands in each control file are considered in the order in which they are given, after all conventional arguments have been processed. It is recommended to use `-args` in all new applications. However, `-control` will be supported for legacy applications.

To avoid interference between `-control` and `AND`, a new mechanism has been added. Using `-args` in place of `-control` will perform direct textual substitution of the file into the command line, prior to any other processing.

1.16 String Arguments

Command lines are handled differently on each operating system. Some characters are reserved with special meanings, even when they occur inside quoted string arguments. To avoid this problem, `cpdf` performs processing on string arguments as they are read.

A backslash is used to indicate that a character which would otherwise be treated specially by the command line interpreter is to be treated literally. For example, Unix-like systems attribute a special meaning to the exclamation mark, so the command line

```
cpdf -add-text "Hello!" in.pdf -o out.pdf
```

would fail. We must escape the exclamation mark with a backslash:

```
cpdf -add-text "Hello\!" in.pdf -o out.pdf
```

It follows that backslashes intended to be taken literally must themselves be escaped (i.e. written `\\`).

1.17 Text Encodings

Some `cpdf` commands write text to standard output, or read text from the command line or configuration files. These are:

```
-info  
-list-bookmarks  
-set-author et al.  
-list-annotations  
-dump-attachments
```

There are three options to control how the text is interpreted:

```
-utf8  
-stripped  
-raw
```

Add `-utf8` to use Unicode UTF8, `-stripped` to convert to 7 bit ASCII by dropping any high characters, or `-raw` to perform no processing. The default unless specified in the documentation for an individual operation is `-stripped`.

1.18 Font Embedding

Use the `-no-embed-font` to avoid embedding the Standard 14 Font metrics when adding text with `-add-text`.

1.19 Creating a new PDF

`Cpdf` can build a new PDF file, given a number of pages and a paper size. The default is one page, A4 portrait.

```
cpdf -create-pdf -create-pdf-pages 20  
      -create-pdf-papersize usletterportrait -o out.pdf
```

The standard paper sizes are listed in Section 3.1, or you may specify the width and height directly, as described in the same chapter.

Chapter 2

Merging and Splitting

```
cpdf -merge in1.pdf [<range>] in2.pdf [<range>] [<more names/ranges>]  
    [-retain-numbering] [-remove-duplicate-fonts]  
    [-merge-add-bookmarks] [-merge-add-bookmarks-use-titles]  
    -o out.pdf  
  
cpdf -split in.pdf -o <format> [-chunk <chunksize>]  
cpdf -split-bookmarks <level> in.pdf -o <format>
```

2.1 Merging

The `-merge` operation allow the merging of several files into one. Ranges can be used to select only a subset of pages from each input file in the output. The output file consists of the concatenation of all the input pages in the order specified on the command line. Actually, the `-merge` can be omitted, since this is the default operation of `cpdf`.

```
cpdf -merge a.pdf 1 b.pdf 2-end -o out.pdf
```

Take page one of `a.pdf` and all but the first page of `b.pdf`, merge them and produce `out.pdf`.

Merge maintains bookmarks, named destinations, and name dictionaries.

Forms and other objects which cannot be merged are retained if they are from the document which first exhibits that feature.

The `-retain-numbering` option keeps the PDF page numbering labels of each document intact, rather than renumbering the output pages from 1.

The `-remove-duplicate-fonts` option ensures that fonts used in more than one of the inputs only appear once in the output.

The `-merge-add-bookmarks` option adds a top-level bookmark for each file, using the filename. Any existing bookmarks are retained. Adding `-merge-add-bookmarks-use-titles` will use the title from each PDF's metadata instead of the filename.

2.2 Splitting

The `-split` operation splits a PDF file into a number of parts which are written to file, their names being generated from a *format*. The optional `-chunk` option allows the number of pages written to each output file to be set.

```
cpdf -split a.pdf -o out%%.pdf
```

Split a.pdf to the files out001.pdf, out002.pdf etc.

```
cpdf -split a.pdf 1 even -chunk 10 -o dir/out%%.pdf
```

Split the even pages of a.pdf to the files out001.pdf, out002.pdf etc. with at most ten pages in each file. The directory (folder) dir must exist.

If the output format does not provide enough numbers for the files generated, the result is unspecified. The following format operators may be used:

<code>%</code> , <code>%%</code> , <code>%%%</code> etc.	Sequence number padded to the number of percent signs
<code>@F</code>	Original filename without extension
<code>@N</code>	Sequence number without padding zeroes
<code>@S</code>	Start page of this chunk
<code>@E</code>	End page of this chunk
<code>@B</code>	Bookmark name at this page

Numbers padded to a fixed width field by zeroes may be obtained for `@S` and `@E` by following them with more `@` signs e.g. `@E@@@` for a fixed width of three.

2.3 Splitting on Bookmarks

The `-split-bookmarks <level>` operation splits a PDF file into a number of parts, according to the page ranges implied by the document's bookmarks. These parts are then written to file with names generated from the given format.

Level 0 denotes the top-level bookmarks, level 1 the next level (sub-bookmarks) and so on. So `-split-bookmarks 1` creates breaks on level 0 and level 1 boundaries.

```
cpdf -split-bookmarks 0 a.pdf -o out%%.pdf
```

Split a.pdf to the files out001.pdf, out002.pdf on bookmark boundaries.

Now, there may be many bookmarks on a single page (for instance, if paragraphs are bookmarked or there are two subsections on one page). The splits calculated by `-split-bookmarks`

ensure that each page appears in only one of the output files. It is possible to use the @ operators above, including operator @B which expands to the text of the bookmark:

```
cpdf -split-bookmarks 0 a.pdf -o @B.pdf
```

Split a.pdf on bookmark boundaries, using the bookmark text as the filename.

The bookmark text used for a name is converted from unicode to 7 bit ASCII, and the following characters are removed, in addition to any character with ASCII code less than 32:

```
/ ? < > \ : * | " ^ + =
```

2.4 Encrypting with Split and Split Bookmarks

The encryption parameters described in Chapter 4 may be added to the command line to encrypt each split PDF. Similarly, the `-recrypt` switch described in 1 may be given to re-encrypt each file with the existing encryption of the source PDF.

Chapter 3

Pages

```
cpdf -scale-page "<scale x> <scale y>" [-fast] in.pdf [<range>] -o out.pdf
cpdf -scale-to-fit "<x size> <y size>" [-fast]
    [-scale-to-fit-scale <scale>]
    in.pdf [<range>] -o out.pdf
cpdf -scale-contents [<scale>] [<position>] [-fast]
    in.pdf [<range>] -o out.pdf
cpdf -shift "<shift x> <shift y>" [-fast] in.pdf [<range>] -o out.pdf
cpdf -rotate <angle> in.pdf [<range>] -o out.pdf
cpdf -rotateby <angle> in.pdf [<range>] -o out.pdf
cpdf -rotate-contents <angle> [-fast] in.pdf [<range>] -o out.pdf
cpdf -upright [-fast] in.pdf [<range>] -o out.pdf
cpdf -hflip [-fast] in.pdf [<range>] -o out.pdf
cpdf -vflip [-fast] in.pdf [<range>] -o out.pdf
cpdf -mediabox "<x> <y> <w> <h>" in.pdf [<range>] -o out.pdf
cpdf -cropbox "<x> <y> <w> <h>" in.pdf [<range>] -o out.pdf
cpdf -remove-cropbox in.pdf [<range>] -o out.pdf
    (Also bleed, art, and trim versions of these two commands, for example -artbox,
    -remove-trimbox)
cpdf -frombox <boxname> -tobox <boxname> [-mediabox-if-missing]
    in.pdf [<range>] -o out.pdf
cpdf -hard-box <boxname> [-fast] in.pdf [<range>]
    [-mediabox-if-missing] -o out.pdf
cpdf -show-boxes [-fast] in.pdf [<range>] -o out.pdf
cpdf -trim-marks [-fast] in.pdf [<range>] -o out.pdf
```

3.1 Page Sizes

Any time when a page size is required, instead of writing, for instance "210mm 197mm" one can instead write `a4portrait`. Here is a list of supported page sizes:

<code>a0portrait</code>	<code>a1portrait</code>	<code>a2portrait</code>
<code>a3portrait</code>	<code>a4portrait</code>	<code>a5portrait</code>
<code>a6portrait</code>	<code>a7portrait</code>	<code>a8portrait</code>
<code>a9portrait</code>	<code>a10portrait</code>	
<code>a0landscape</code>	<code>a1landscape</code>	<code>a2landscape</code>
<code>a3landscape</code>	<code>a4landscape</code>	<code>a5landscape</code>
<code>a6landscape</code>	<code>a7landscape</code>	<code>a8landscape</code>
<code>a9landscape</code>	<code>a10landscape</code>	
<code>usletterportrait</code>	<code>usletterlandscape</code>	
<code>uslegalportrait</code>	<code>uslegallandscape</code>	

3.2 Scale Pages

The `-scale-page` operation scales each page in the range by the X and Y factors given. This scales both the page contents, and the page size itself. It also scales any Crop Box and other boxes (Art Box, Trim Box etc). As with several of these commands, remember to take into account any page rotation when considering what the X and Y axes relate to.

```
cpdf -scale-page "2 2" in.pdf -o out.pdf
```

Convert an A4 page to A3, for instance.

The `-scale-to-fit` operation scales each page in the range to fit a given page size, preserving aspect ratio and centering the result.

```
cpdf -scale-to-fit "297mm 210mm" in.pdf -o out.pdf
cpdf -scale-to-fit a4portrait in.pdf -o out.pdf
```

Scale a file's pages to fit A4 portrait.

The scale can optionally be set to a percentage of the available area, instead of filling it.

```
cpdf -scale-to-fit a4portrait -scale-to-fit-scale 0.9 in.pdf -o out.pdf
```

Scale a file's pages to fit A4 portrait, scaling the page 90% of its possible size.

NB: `-scale-to-fit` operates with respect to the media box not the crop box. If necessary, set the media box to be equal to the crop box first. In addition, `-scale-to-fit` presently requires that the origin of the media box be (0, 0). This can be assured by preprocessing with `-upright`.

The `-scale-contents` operation scales the contents about the center of the crop box (or, if absent, the media box), leaving the page dimensions (boxes) unchanged.

```
cpdf -scale-contents 0.5 in.pdf -o out.pdf
```

Scale a file's contents on all pages to 50% of its original dimensions.

To scale about a point other than the center, one can use the positioning commands described in Section 8.2.4. For example:

```
cpdf -scale-contents 0.5 -topright 20 in.pdf -o out.pdf
```

Scale a file's contents on all pages to 50% of its original dimensions about a point 20pts from its top right corner.

3.3 Shift Page Contents

The `-shift` operation shifts the contents of each page in the range by X points horizontally and Y points vertically.

```
cpdf -shift "50 0" in.pdf even -o out.pdf
```

Shift pages to the right by 50 points (for instance, to increase the binding margin).

3.4 Rotating Pages

There are two ways of rotating pages: (1) setting a value in the PDF file which asks the viewer (e.g. Acrobat) to rotate the page on-the-fly when viewing it (use `-rotate` or `-rotateby`) and (2) actually rotating the page contents and/or the page dimensions (use `-upright` afterwards or `-rotate-contents` to just rotate the page contents).

The possible values for `-rotate` and `-rotateby` are 0, 90, 180 and 270, all interpreted as being clockwise. Any value may be used for `-rotate-contents`.

The `-rotate` operation sets the viewing rotation of the selected pages to the absolute value given.

```
cpdf -rotate 90 in.pdf -o out.pdf
```

Set the rotation of all the pages in the input file to ninety degrees clockwise.

The `-rotateby` operation changes the viewing rotation of all the given pages by the relative value given.

```
cpdf -rotateby 90 in.pdf -o out.pdf
```

Rotate all the pages in the input file by ninety degrees clockwise.

The `-rotate-contents` operation rotates the contents and dimensions of the page by the given relative value.

```
cpdf -rotate-contents 90 in.pdf -o out.pdf
```

Rotate all the page contents in the input file by ninety degrees clockwise. Does not change the page dimensions.

The `-upright` operation does whatever combination of `-rotate` and `-rotate-contents` is required to change the rotation of the document to zero without altering its appearance. In addition, it makes sure the media box has its origin at (0,0), changing other boxes to compensate. This is important because some operations in CPDF (such as `scale-to-fit`), and in other PDF-processing programs, work properly only when the origin is (0, 0).

3.5 Flipping Pages

The `-hflip` and `-vflip` operations flip the contents of the chosen pages horizontally or vertically. No account is taken of the current page rotation when considering what “horizontally” and “vertically” mean, so you may like to use `-upright` first.

```
cpdf -hflip in.pdf even -o out.pdf
```

Flip the even pages in `in.pdf` horizontally.

```
cpdf -vflip in.pdf -o out.pdf
```

Flip all the pages in `in.pdf` vertically.

3.6 Boxes and Cropping

All PDF files contain a *media box* for each page, giving the dimensions of the paper. To change these dimensions (without altering the page contents in any way), use the `-mediabox` operation.

```
cpdf -mediabox "0pt 0pt 500pt 500pt" in.pdf -o out.pdf
```

Set the media box to 500 points square.

The four numbers are minimum x, minimum y, width, height. x coordinates increase to the right, y coordinates increase upwards. PDF file can also optionally contain a *crop box* for each

page, defining to what extent the page is cropped before being displayed or printed. A crop box can be set, changed and removed, without affecting the underlying media box. To set or change the crop box use `-cropbox`. To remove any existing crop box, use `-remove-cropbox`.

```
cpdf -cropbox "0pt 0pt 200mm 200mm" in.pdf -o out.pdf
```

Crop pages to the bottom left 200-millimeter square of the page.

```
cpdf -remove-cropbox in.pdf -o out.pdf
```

Remove cropping.

Note that the crop box is only obeyed in some viewers. Similar operations are available for the bleed, art, and trim boxes (`-art`, `-remove-bleed` etc.)

```
cpdf -frombox <boxname> -tobox <boxname> [-mediabox-if-missing]  
in.pdf [<range>] -o out.pdf
```

Copy the contents of one box to another.

This operation copies the contents of one box (Media box, Crop box, Trim box etc.) to another. If `-mediabox-if-missing` is added, the media box will be substituted when the 'from' box is not set for a given page. For example

```
cpdf -frombox /TrimBox -tobox /CropBox in.pdf -o out.pdf
```

copies the Trim Box of each page to the Crop Box of each page. The possible boxes are `/MediaBox`, `/CropBox`, `/BleedBox`, `/TrimBox`, `/ArtBox`.

A hard box (one which clips its contents by inserting a clipping rectangle) may be created with the `-hard-box` operation:

```
cpdf -hard-box /TrimBox in.pdf -o out.pdf
```

This means the resultant file may be used as a stamp without contents outside the given box reappearing. The `-mediabox-if-missing` option may also be used here.

3.7 Showing Boxes and Printer's Marks

The `-show-boxes` operation displays the boxes present on each page as method of debugging. Since boxes may be coincident, they are shown in differing colours and dash patterns so they may be identified even where they overlap. The colours are:

Media box	Red
Crop box	Green
Art box	Blue
Trim box	Orange
Bleed box	Pink

The `-trim-marks` operation adds trim marks to a PDF file. The trim box must be present.

Chapter 4

Encryption and Decryption

```
cpdf -encrypt <method> <owner> <user>  
      [-no-encrypt-metadata] <permissions> in.pdf -o out.pdf  
cpdf -decrypt in.pdf owner=<owner password> -o out.pdf
```

4.1 Introduction

PDF files can be encrypted using various types of encryption and attaching various permissions describing what someone can do with a particular document (for instance, printing it or extracting content). There are two types of person:

The **User** can do to the document what is allowed in the permissions.

The **Owner** can do anything, including altering the permissions or removing encryption entirely.

There are five kinds of encryption:

- 40-bit encryption (method 40bit) in Acrobat 3 (PDF 1.1) and above
- 128-bit encryption (method 128bit) in Acrobat 5 (PDF 1.4) and above
- 128-bit AES encryption (method AES) in Acrobat 7 (PDF 1.6) and above
- 256-bit AES encryption (method AES256) in Acrobat 9 (PDF 1.7) – *this is deprecated – do not use for new documents*
- 256-bit AES encryption (method AES256ISO) in PDF 2.0

All encryption supports these kinds of permissions:

-no-edit	Cannot change the document
-no-print	Cannot print the document
-no-copy	Cannot select or copy text or graphics
-no-annot	Cannot add or change form fields or annotations

In addition, 128-bit encryption (Acrobat 5 and above) and AES encryption supports these:

<code>-no-forms</code>	Cannot edit form fields
<code>-no-extract</code>	Cannot extract text or graphics
<code>-no-assemble</code>	Cannot merge files etc.
<code>-no-hq-print</code>	Cannot print high-quality

Add these options to the command line to prevent each operation.

4.2 Encrypting a Document

To encrypt a document, the owner and user passwords must be given (here, `fred` and `charles` respectively):

```
cpdf -encrypt 40bit fred charles -no-print in.pdf -o out.pdf
cpdf -encrypt 128bit fred charles -no-extract in.pdf -o out.pdf
cpdf -encrypt AES fred "" -no-edit -no-copy in.pdf -o out.pdf
```

A blank user password is common. In this event, PDF viewers will typically not prompt for a password for when opening the file or for operations allowable with the user password.

```
cpdf -encrypt AES256 fred "" -no-forms in.pdf -o out.pdf
```

In addition, the usual method can be used to give the existing owner password, if the document is already encrypted.

When using AES encryption, the option is available to refrain from encrypting the metadata. Add `-no-encrypt-metadata` to the command line.

4.3 Decrypting a Document

To decrypt a document, the owner password is provided.

```
cpdf -decrypt in.pdf owner=fred -o out.pdf
```

The user password cannot decrypt a file.

Chapter 5

Compression

```
cpdf -decompress in.pdf -o out.pdf
cpdf -compress in.pdf -o out.pdf
cpdf -squeeze in.pdf [-squeeze-log-to <filename>]
    [-squeeze-no-recompress] [-squeeze-no-page-data] -o out.pdf
```

`cpdf` provides basic facilities for decompressing and compressing PDF streams, and for reprocessing the whole file to ‘squeeze’ it.

5.1 Decompressing a Document

To decompress the streams in a PDF file, for instance to manually inspect the PDF, use:

```
cpdf -decompress in.pdf -o out.pdf
```

If `cpdf` finds a compression type it can’t cope with, the stream is left compressed. When using `-decompress`, object streams are not compressed. It may be easier for manual inspection to also remove object streams, by adding the `-no-preserve-objstm` option to the command.

5.2 Compressing a Document

To compress the streams in a PDF file, use:

```
cpdf -compress in.pdf -o out.pdf
```

`cpdf` compresses any streams which have no compression using the **FlateDecode** method, with the exception of Metadata streams, which are left uncompressed.

5.3 Squeezing a Document

To *squeeze* a PDF file, reducing its size by an average of about twenty percent (though sometimes not at all), use:

```
cpdf -squeeze in.pdf -o out.pdf
```

Adding `-squeeze` to the command line when using another operation will *squeeze* the file or files upon output.

The `-squeeze` operation writes some information about the squeezing process to standard output. The squeezing process involves several processes which losslessly attempt to reduce the file size. It is slow, so should not be used without thought.

```
$ ./cpdf -squeeze in.pdf -o out.pdf
Initial file size is 238169 bytes
Beginning squeeze: 123847 objects
Squeezing... Down to 114860 objects
Squeezing... Down to 114842 objects
Squeezing page data
Recompressing document
Final file size is 187200 bytes, 78.60% of original.
```

The `-squeeze-log-to <filename>` option writes the log to the given file instead of to standard output. Log contents is appended to the end of the log file, preserving existing contents.

There are two options which turn off parts of the squeezer. They are `-squeeze-no-recompress` for avoiding the reprocessing of malformed compressed sections, and `-squeeze-no-page-data` for avoiding the reprocessing of malformed page data.

Chapter 6

Bookmarks

```
cpdf -list-bookmarks [-utf8 | -raw] in.pdf
cpdf -remove-bookmarks in.pdf -o out.pdf
cpdf -add-bookmarks <bookmark file> in.pdf -o out.pdf
cpdf -bookmarks-open-to-level <n> in.pdf -o out.pdf
```

PDF Bookmarks (properly called the *document outline*) represent a tree of references to parts of the file, typically displayed at the side of the screen. The user can click on one to move to the specified place. `cpdf` provides facilities to list, add, and remove bookmarks. The format used by the list and add operations is the same, so you can feed the output of one into the other, for instance to copy bookmarks.

6.1 List Bookmarks

The `-list-bookmarks` operation prints (to standard output) the bookmarks in a file. The first column gives the level of the tree at which a particular bookmark is. Then the text of the bookmark in quotes. Then the page number which the bookmark points to. Then (optionally) the word “open” if the bookmark should have its children (at the level immediately below) visible when the file is loaded. Then the destination (see below). For example, upon executing

```
cpdf -list-bookmarks doc.pdf
```

the result might be:

```
0 "Part 1" 1 open
1 "Part 1A" 2 "[2 /XYZ 200 400 null]"
1 "Part 1B" 3
```

```
0 "Part 2" 4
1 "Part 2a" 5
```

If the page number is 0, it indicates that clicking on that entry doesn't move to a page.

By default, `cpdf` converts unicode to ASCII text, dropping characters outside the ASCII range. To prevent this, and return unicode UTF8 output, add the `-utf8` option to the command. To prevent any processing, use the `-raw` option. See Section 1.17 for more information. A newline in a bookmark is represented as `"\n"`.

6.1.1 Destinations

The destination is an extended description of where the bookmark should point to (i.e it can be more detailed than just giving the page). For example, it may point to a section heading halfway down a page. Here are the possibilities:

Format	Description
<code>[p /XYZ left top zoom]</code>	Display page number <i>p</i> with (<i>left</i> , <i>top</i>) positioned at upper-left of window and magnification of <i>zoom</i> . Writing "null" for any of <i>left</i> , <i>top</i> or <i>zoom</i> specifies no change. A <i>zoom</i> of 0 is the same as "null".
<code>[p /Fit]</code>	Display page number <i>p</i> so as to fit fully within the window.
<code>[p /FitH top]</code>	Display page number <i>p</i> with vertical coordinate <i>top</i> at the top of the window and the page magnified so its width fits the window. A null value for <i>top</i> implies no change.
<code>[p /FitV left]</code>	Display page number <i>p</i> with horizontal coordinate <i>left</i> at the left of the window, and the page magnified so its height fits the window. A null value for <i>left</i> implies no change.
<code>[p /FitR left bottom right top]</code>	Display page number <i>p</i> magnified so as to fit entirely within the rectangle specified by the other parameters.
<code>[p /FitB]</code>	As for /Fit but with the page's bounding box (see below).
<code>[p /FitBH top]</code>	As for /FitH but with the page's bounding box (see below).
<code>[p /FitBV left]</code>	As for /FitV but with the page's bounding box (see below).

The *bounding box* is the intersection of the page's crop box and the bounding box of the page contents. Some other kinds of destination may be produced by `-list-bookmarks`. They will be preserved by `-add-bookmarks` and may be edited at your risk.

6.2 Remove Bookmarks

The `-remove-bookmarks` operation removes all bookmarks from the file.

```
cpdf -remove-bookmarks in.pdf -o out.pdf
```

6.3 Add Bookmarks

The `-add-bookmarks` operation adds bookmarks as specified by a *bookmarks file*, a text file in ASCII or UTF8 encoding and in the same format as that produced by the `-list-bookmarks` operation. If there are any bookmarks in the input PDF already, they are discarded. For example, if the file `bookmarks.txt` contains the output from `-list-bookmarks` above, then the command

```
cpdf -add-bookmarks bookmarks.txt in.pdf -o out.pdf
```

adds the bookmarks to the input file, writing to `out.pdf`. An error will be given if the bookmarks file is not in the correct form (in particular, the numbers in the first column which specify the level must form a proper tree with no entry being more than one greater than the last).

6.4 Opening bookmarks

As an alternative to extracting a bookmark file and manipulating the open-status of bookmarks, mass manipulation may be achieved by the following operation:

```
cpdf -bookmarks-open-to-level <level> in.pdf -o out.pdf
```

A level of 0 will close all bookmarks, level 1 will open just the top level, closing all others etc. To open all of them, pick a sufficiently large level.

Chapter 7

Presentations

```
cpdf -presentation in.pdf [<range>] -o out.pdf
      [-trans <transition-name>] [-duration <float>]
      [-vertical] [-outward] [-direction <int>]
      [-effect-duration <float>]
```

The PDF file format, starting at Version 1.1, provides for simple slide-show presentations in the manner of Microsoft Powerpoint. These can be played in Acrobat and possibly other PDF viewers, typically started by entering full-screen mode. The `-presentation` operation allows such a presentation to be built from any PDF file.

The `-trans` option chooses the transition style. When a page range is used, it is the transition *from* each page named which is altered. The following transition styles are available:

Split Two lines sweep across the screen, revealing the new page. By default the lines are horizontal. Vertical lines are selected by using the `-vertical` option.

Blinds Multiple lines sweep across the screen, revealing the new page. By default the lines are horizontal. Vertical lines are selected by using the `-vertical` option.

Box A rectangular box sweeps inward from the edges of the page. Use `-outward` to make it sweep from the center to the edges.

Wipe A single line sweeps across the screen from one edge to the other in a direction specified by the `-direction` option.

Dissolve The old page dissolves gradually to reveal the new one.

Glitter The same as **Dissolve** but the effect sweeps across the page in the direction specified by the `-direction` option.

To remove a transition style currently applied to the selected pages, omit the `-trans` option.

The `-effect-duration` option specifies the length of time in seconds for the transition itself. The default value is one second.

The `-duration` option specifies the maximum time in seconds that the page is displayed before the presentation automatically advances. The default, in the absence of the `-duration` option, is for no automatic advancement.

The `-direction` option (for **Wipe** and **Glitter** styles only) specifies the direction of the effect. The following values are valid:

0 Left to right

90 Bottom to top (**Wipe** only)

180 Right to left (**Wipe** only)

270 Top to bottom

315 Top-left to bottom-right (**Glitter** only)

For example:

```
cpdf -presentation in.pdf 2-end -trans Split -duration 10 -o out.pdf
```

The **Split** style, with vertical lines, and each slide staying ten seconds unless manually advanced. The first page (being a title) does not move on automatically, and has no transition effect.

To use different options on different page ranges, run `cpdf` multiple times on the file using a different page range each time.

Chapter 8

Watermarks and Stamps

```
cpdf -stamp-on source.pdf
    [-scale-stamp-to-fit] [<positioning command>] [-relative-to-cropbox]
    in.pdf [<range>] [-fast] -o out.pdf

cpdf -stamp-under source.pdf
    [-scale-stamp-to-fit] [<positioning command>] [-relative-to-cropbox]
    in.pdf [<range>] [-fast] -o out.pdf

cpdf -combine-pages over.pdf under.pdf [-fast] -o out.pdf

cpdf ([-add-text <text-format> | -add-rectangle <size>])
    [-font <fontname>]
    [-font-size <size-in-points>]
    [-color <color>]
    [-line-spacing <number>]
    [-outline]
    [-linewidth <number>]
    [-underneath]
    [-relative-to-cropbox]
    [-prerotate]
    [-bates <number>]
    [-bates-at-range <number>]
    [-bates-pad-to <number>]
    [-opacity <number>]
    [-midline]
    [-topline]
    [-fast]
    in.pdf [<range>] -o out.pdf
```

See also positioning commands below.

```
cpdf -remove-text in.pdf [<range>] -o out.pdf
```

NB: See discussion of `-fast` in Section 1.13.

8.1 Add a Watermark or Logo

The `-stamp-on` and `-stamp-under` operations stamp the first page of a source PDF onto or under each page in the given range of the input file. For example,

```
cpdf -stamp-on logo.pdf in.pdf odd -o out.pdf
```

stamps the file `logo.pdf` onto the odd pages of `in.pdf`, writing to `out.pdf`. A watermark should go underneath each page:

```
cpdf -stamp-under topsecret.pdf in.pdf -o out.pdf
```

The position commands in Section 8.2.4 can be used to locate the stamp more precisely (they are calculated relative to the crop box of the stamp). Or, preprocess the stamp with `-shift` first.

The `-scale-stamp-to-fit` option can be added to scale the stamp to fit the page before applying it. The use of positioning commands together with `-scale-stamp-to-fit` is not recommended.

The `-combine-pages` operation takes two PDF files and stamps each page of one over each page of the other. The length of the output is the same as the length of the “under” file. For instance:

```
cpdf -combine-pages over.pdf under.pdf -o out.pdf
```

Page attributes (such as the display rotation) are taken from the “under” file. For best results, remove any rotation differences in the two files using `-upright` first.

The `-relative-to-cropbox` option takes the positioning command to be relative to the crop box of each page rather than the media box.

8.2 Stamp Text, Dates and Times.

The `-add-text` operation allows text, dates and times to be stamped over one or more pages of the input at a given position and using a given font, font size and color.

```
cpdf -add-text "Copyright 2014 ACME Corp." in.pdf -o out.pdf
```

The default is black 12pt Times New Roman text in the top left of each page. The text can be placed underneath rather than over the page by adding the `-underneath` option.

Text previously added by `cpdf` may be removed by the `-remove-text` operation.

```
cpdf -remove-text in.pdf -o out.pdf
```

8.2.1 Page Numbers

There are various special codes to include the page number in the text:

%Page	Page number in arabic notation (1, 2, 3...)
%PageDiv2	Page number in arabic notation divided by two
%roman	Page number in lower-case roman notation (i, ii, iii...)
%Roman	Page number in upper-case roman notation (I, II, III...)
%EndPage	Last page of document in arabic notation
%Label	The page label of the page
%EndLabel	The page label of the last page
%filename	The full file name of the input document

For example, the format "Page %Page of %EndPage" might become "Page 5 of 17".

NB: In some circumstances (e.g in batch files) on Microsoft Windows, % is a special character, and must be escaped (written as %%). Consult your local documentation for details.

8.2.2 Date and Time Formats

%a	Abbreviated weekday name (Sun, Mon etc.)
%A	Full weekday name (Sunday, Monday etc.)
%b	Abbreviated month name (Jan, Feb etc.)
%B	Full month name (January, February etc.)
%d	Day of the month (01–31)
%e	Day of the month (1–31)
%H	Hour in 24-hour clock (00–23)
%I	Hour in 12-hour clock (01–12)
%j	Day of the year (001–366)
%m	Month of the year (01–12)
%M	Minute of the hour (00–59)
%p	"a.m" or "p.m"
%S	Second of the minute (00–61)
%T	Same as %H:%M:%S
%u	Weekday (1–7, 1 = Monday)
%w	Weekday (0–6, 0 = Monday)
%Y	Year (0000–9999)
%%	The % character.

8.2.3 Bates Numbers

Unique page identifiers can be specified by putting %Bates in the format. The starting point can be set with the -bates option. For example:

```
cpdf -add-text "Page ID: %Bates" -bates 23745 in.pdf -o out.pdf
```

To specify that bates numbering begins at the first page of the range, use -bates-at-range instead. This option must be specified after the range is specified. To pad the bates number

up to a given number of leading zeros, use `-bates-pad-to` in addition to either `-bates` or `-bates-at-range`.

8.2.4 Position

The position of the text may be specified either in absolute terms:

```
-pos-center "200 200"
```

Position the center of the baseline text at (200pt, 200pt)

```
-pos-left "200 200"
```

Position the left of the baseline of the text at (200pt, 200pt)

```
-pos-right "200 200"
```

Position the right of the baseline of the text at (200pt, 200pt)

Positions relative to certain common points can be set:

<code>-top 10</code>	Center of baseline 10 pts down from the top center
<code>-topleft 10</code>	Left of baseline 10 pts down and in from top left
<code>-topright 10</code>	Right of baseline 10 pts down and left from top right
<code>-left 10</code>	Left of baseline 10 pts in from center left
<code>-bottomleft 10</code>	Left of baseline 10 pts in and up from bottom left
<code>-bottom 10</code>	Center of baseline 10 pts up from bottom center
<code>-bottomright 10</code>	Right of baseline 10 pts up and in from bottom right
<code>-right 10</code>	Right of baseline 10 pts in from the center right
<code>-diagonal</code>	Diagonal, bottom left to top right, centered on page
<code>-reverse-diagonal</code>	Diagonal, top left to bottom right, centered on page
<code>-center</code>	Centered on page

No attempt is made to take account of the page rotation when interpreting the position, so `-prerotate` must be added to the command line if the file contains pages with a non-zero viewing rotation. This is equivalent to pre-processing the document with `-upright`.

The `-relative-to-cropbox` modifier can be added to the command line to make these measurements relative to the crop box instead of the media box.

The default position is equivalent to `-topleft 100`.

The `-midline` option may be added to specify that the positioning commands above are to be considered relative to the midline of the text, rather than its baseline. Similarly, the `-topline` option may be used to specify that the position is taken relative to the top of the text.

8.2.5 Font and Size

The font may be set with the `-font` option. The 14 Standard PDF fonts are available:

Times-Roman
 Times-Bold
 Times-Italic
 Times-BoldItalic
 Helvetica
 Helvetica-Bold
 Helvetica-Oblique
 Helvetica-BoldOblique
 Courier
 Courier-Bold
 Courier-Oblique
 Courier-BoldOblique
 Symbol
 ZapfDingbats

For example, page numbers in Times Italic can be achieved by:

```
cpdf -add-text "-%Page-" -font "Times-Italic" in.pdf -o out.pdf
```

See Section 14.2 for how to use other fonts. The font size can be altered with the `-font-size` option, which specifies the size in points:

```
cpdf -add-text "-%Page-" -font-size 36 in.pdf -o out.pdf
```

8.2.6 Colors

The `-color` option takes an RGB color, where red, green and blue components range between 0 and 1. The following values are predefined:

Color	R, G, B
white	1, 1, 1
black	0, 0, 0
red	1, 0, 0
green	0, 1, 0
blue	0, 0, 1

```
cpdf -add-text "Hullo" -color "red" in.pdf -o out.pdf
cpdf -add-text "Hullo" -color "0.5 0.5 0.5" in.pdf -o out.pdf
```

Partly-transparent text may be specified using the `-opacity` option. Wholly opaque is 1 and wholly transparent is 0. For example:

```
cpdf -add-text "DRAFT" -color "red" -opacity 0.3 -o out.pdf
```

8.2.7 Outline Text

The `-outline` option sets outline text. The line width (default 1pt) may be set with the `-linewidth` option. For example, to stamp documents as drafts:

```
cpdf -add-text "DRAFT" -diagonal -outline in.pdf -o out.pdf
```

8.2.8 Multi-line Text

The code `\n` can be included in the text string to move to the next line. In this case, the vertical position refers to the baseline of the first line of text (if the position is at the top, top left or top right of the page) or the baseline of the last line of text (if the position is at the bottom, bottom left or bottom right).

```
cpdf -add-text "Specification\n%Page of %EndPage"  
-topright 10 in.pdf -o out.pdf
```

The `-midline` option may be used to make these vertical positions relative to the midline of a line of text rather than the baseline, as usual.

The `-line-spacing` option can be used to increase or decrease the line spacing, where a spacing of 1 is the standard.

```
cpdf -add-text "Specification\n%Page of %EndPage"  
-topright 10 -line-spacing 1.5 in.pdf -o out.pdf
```

Justification of multiple lines is handled by the `-justify-left`, `-justify-right` and `-justify-center` options. The defaults are left justification for positions relative to the left hand side of the page, right justification for those relative to the right, and center justification for positions relative to the center of the page. For example:

```
cpdf -add-text "Long line\nShort" -justify-right  
in.pdf -o out.pdf
```

8.2.9 Special Characters

If your command line allows for the inclusion of unicode characters, the input text will be considered as UTF8 by `cpdf`. Special characters which exist in the PDF WinAnsiEncoding Latin

1 code (such as many accented characters) will be reproduced in the PDF. This does not mean, however, that every special character can be reproduced. You must experiment.

For compatibility with previous versions of cpdf, special characters may be introduced manually with a backslash followed by the three-digit octal code of the character in the PDF WinAnsiEncoding Latin 1 Code. The full table is included in Appendix D of the Adobe PDF Reference Manual, which is available at http://www.adobe.com/devnet/pdf/pdf_reference.html.

For example, a German sharp s (ß) may be introduced by `\337`.

8.3 Stamping Graphics

A rectangle may be placed on one or more pages by using the `-add-rectangle <size>` command. Most of the options discussed above for text placement apply in the same way. For example:

```
cpdf -add-rectangle "200 300" -pos-right 30 -color red -outline  
in.pdf -o out.pdf
```

This can be used to blank out or highlight part of the document. The following positioning options work as you would expect: `-topleft`, `-top`, `-topright`, `-right`, `-bottomright`, `-bottom`, `-bottomleft`, `-left`, `-center`. When using the option `-pos-left "x y"`, the point (x, y) refers to the bottom-left of the rectangle. When using the option `-pos-right "x y"`, the point (x, y) refers to the bottom-right of the rectangle. When using the option `-pos-center "x y"`, the point (x, y) refers to the center of the rectangle. The options `-diagonal` and `-reverse-diagonal` have no meaning.

Chapter 9

Multipage Facilities

```
cpdf -twoup-stack [-fast] in.pdf -o out.pdf
cpdf -twoup [-fast] in.pdf -o out.pdf
cpdf -pad-before in.pdf [<range>] [-pad-with pad.pdf] -o out.pdf
cpdf -pad-after in.pdf [<range>] [-pad-with pad.pdf] -o out.pdf
cpdf -pad-every [<integer>] in.pdf [-pad-with pad.pdf] -o out.pdf
cpdf -pad-multiple [<integer>] in.pdf -o out.pdf
cpdf -pad-multiple-before [<integer>] in.pdf -o out.pdf
```

9.1 Two-up

This facility puts multiple logical pages on a single physical page. The `-twoup-stack` operation puts two logical pages on each physical page, rotating them 90 degrees to do so. The new mediabox is thus larger. The `-twoup` operation does the same, but scales the new sides down so that the media box is unchanged.

NB: See discussion of `-fast` in Section 1.13.

9.2 Inserting Blank Pages

Sometimes, for instance to get a printing arrangement right, it's useful to be able to insert blank pages into a PDF file. `cpdf` can add blank pages before a given page or pages, or after. The pages in question are specified by a range in the usual way:

```
cpdf -pad-before in.pdf 1 -o out.pdf
```

Add a blank page before page 1 (i.e. at the beginning of the document.)

```
cpdf -pad-after in.pdf 2,16,38,84,121,147 -o out.pdf
```

Add a blank page after pages 2, 16, 38, 84, 121 and 147 (for instance, to add a clean page between chapters of a document.)

The dimensions of the padded page are derived from the boxes (media box, crop box etc.) of the page after or before which the padding is to be applied.

The `-pad-every n` operation places a blank page after every `n` pages, excluding any last one. For example...

```
cpdf -pad-every 3 in.pdf -o out.pdf
```

Add a blank page after every three pages

...on a 9 page document adds a blank page after pages 3 and 6.

In all three of these operations, one may specify `-pad-with` providing a (usually one-page) PDF file to be used instead of a blank page. For example, a page saying “This page left intentionally blank”.

The `-pad-multiple n` operation adds blank pages so the document has a multiple of `n` pages. For example:

```
cpdf -pad-multiple 8 in.pdf -o out.pdf
```

Add blank pages to `in.pdf` so it has a multiple of 8 pages.

The `-pad-multiple-before n` operation adds the padding pages at the beginning of the file instead.

Chapter 10

Annotations

```
cpdf -list-annotations in.pdf [<range>]
cpdf -copy-annotations from.pdf to.pdf [<range>] -o out.pdf
cpdf -remove-annotations in.pdf [<range>] -o out.pdf
```

10.1 List Annotations

The `-list-annotations` operation prints the textual content of any annotations on the selected pages to standard output. Each annotation is preceded by the page number and followed by a newline. See Section 1.17 for more information on text encodings in the output of this operation.

```
cpdf -list-annotations in.pdf > annots.txt
```

Print annotations from `in.pdf`, redirecting output to `annots.txt`.

10.2 Copy Annotations

The `-copy-annotations` operation copies the annotations in the given page range from one file (the file specified immediately after the option) to another pre-existing PDF. The range is specified after this pre-existing PDF. The result is then written an output file, specified in the usual way.

```
cpdf -copy-annotations from.pdf to.pdf 1-10 -o result.pdf
```

Copy annotations from the first ten pages of `from.pdf` onto the PDF file `to.pdf`, writing the result to `results.pdf`.

10.3 Remove Annotations

The `-remove-annotations` operation removes all annotations from the given page range.

```
cpdf -remove-annotations in.pdf 1 -o out.pdf
```

Remove annotations from the first page of a file only.

Chapter 11

Document Information and Metadata

```
cpdf -info [-raw | -utf8] in.pdf
cpdf -page-info in.pdf
cpdf -pages in.pdf
cpdf -set-title <title of document>
    [-also-set-xmp] [-just-set-xmp] [-raw] in.pdf -o out.pdf
(Also -set-author etc. See Section 11.3.)
cpdf -set-page-layout <layout> in.pdf -o out.pdf
cpdf -set-page-mode <mode> in.pdf -o out.pdf
cpdf -hide-toolbar <true | false> in.pdf -o out.pdf
    -hide-menubar
    -hide-window-ui
    -fit-window
    -center-window
    -display-doc-title
cpdf -open-at-page <page number> in.pdf -o out.pdf
cpdf -open-at-page-fit <page number> in.pdf -o out.pdf
cpdf -set-metadata <metadata-file> in.pdf -o out.pdf
cpdf -remove-metadata in.pdf -o out.pdf
cpdf -print-metadata in.pdf
cpdf -create-metadata in.pdf -o out.pdf
cpdf -set-metadata-date <date> in.pdf -o out.pdf
cpdf -add-page-labels in.pdf -o out.pdf
    [-label-style <style>] [-label-prefix <string>]
    [-label-startval <integer>] [-labels-progress]
```

```
cpdf -remove-page-labels in.pdf -o out.pdf
cpdf -print-page-labels in.pdf
```

11.1 Listing Fonts

11.2 Reading Document Information

The `-info` operation prints entries from the document information dictionary, and from any XMP metadata to standard output.

```
$cpdf -info pdf_reference.pdf
Encryption: 40bit
Linearized: true
Permissions: No edit
Version: 1.6
Pages: 1310
Title: PDF Reference, version 1.7
Author: Adobe Systems Incorporated
Subject: Adobe Portable Document Format (PDF)
Keywords:
Creator: FrameMaker 7.2
Producer: Acrobat Distiller 7.0.5 (Windows)
Created: D:20061017081020Z
Modified: D:20061118211043-02'30'
XMP pdf:Producer: Adobe PDF library 7.77
XMP xmp:CreateDate: 2006-12-21T18:19:09+01:00
XMP xmp:CreatorTool: Adobe Illustrator CS2
XMP xmp:MetadataDate: 2006-12-21T18:19:09Z
XMP xmp:ModifyDate: 2006-12-21T18:19:09Z
XMP dc:title: AI6
```

The details of the format for creation and modification dates can be found in Appendix A.

By default, `cpdf` strips to ASCII, discarding character codes in excess of 127. In order to preserve the original unicode, add the `-utf8` option. To disable all postprocessing of the string, add `-raw`. See Section 1.17 for more information.

The `-page-info` operation prints the page label, media box and other boxes page-by-page to standard output, for all pages in the current range.

```
$cpdf -page-info 14psfonts.pdf
Page 1:
Label: i
```

```

MediaBox: 0.000000 0.000000 600.000000 450.000000
CropBox: 200.000000 200.000000 500.000000 500.000000
BleedBox:
TrimBox:
ArtBox:
Rotation: 0

```

Note that the format for boxes is minimum x, minimum y, maximum x, maximum y.

The `-pages` operation prints the number of pages in the file.

```

cpdf -pages Archos.pdf
8

```

11.3 Setting Document Information

The *document information dictionary* in a PDF file specifies various pieces of information about a PDF. These can be consulted in a PDF viewer (for instance, Acrobat).

Here is a summary of the commands for setting entries in the document information dictionary:

Information	Example command-line fragment
Title	<code>cpdf -set-title "Discourses"</code>
Author	<code>cpdf -set-author "Joe Smith"</code>
Subject	<code>cpdf -set-subject "Behavior"</code>
Keywords	<code>cpdf -set-keywords "Ape Primate"</code>
Creator	<code>cpdf -set-creator "Original Program"</code>
Producer	<code>cpdf -set-producer "Distilling Program"</code>
Creation Date	<code>cpdf -set-create "D:19970915110347-08'00' "</code>
Modification Date	<code>cpdf -set-modify "D:19970915110347-08'00' "</code>
Mark as Trapped	<code>cpdf -set-trapped</code>
Mark as Untrapped	<code>cpdf -set-untrapped</code>

(The details of the format for creation and modification dates can be found in Appendix A. Using the date "now" uses the time and date at which the command is executed. Note also that `-producer` and `-creator` may be used to set the producer and/or the creator when writing any file, separate from the operations described in this chapter.)

For example, to set the title, the full command line would be


```
cpdf -set-title "A Night in London" in.pdf -o out.pdf
```

The text string is considered to be in UTF8 format, unless the `-raw` option is added—in which case, it is unprocessed, save for the replacement of any octal escape sequence such as `\017`, which is replaced by a character of its value (here, 15).

To set also any field in the XMP metadata, add `-also-set-xmp`. The field must exist already. To set only the field (not the document information dictionary), add `-just-set-xmp` instead.

11.4 XMP Metadata

PDF files can contain a piece of arbitrary metadata, often in XMP format. This is typically stored in an uncompressed stream, so that other applications can read it without having to decode the whole PDF. To set the metadata:

```
cpdf -set-metadata data.xml in.pdf -o out.pdf
```

To remove any metadata:

```
cpdf -remove-metadata in.pdf -o out.pdf
```

To print the current metadata to standard output:

```
cpdf -print-metadata in.pdf
```

To create XMP metadata from scratch, using any information in the Document Information Dictionary (old-style metadata):

```
cpdf -create-metadata in.pdf -o out.pdf
```

To set the XMP metadata date field, use:

```
cpdf -set-metadata-date <date> in.pdf -o out.pdf
```

The date format is defined in Appendix A.2. Using the date `"now"` uses the time and date at which the command is executed.

11.5 Upon Opening a Document

11.5.1 Page Layout

The `-set-page-layout` operation specifies the page layout to be used when a document is opened in, for instance, Acrobat. The possible (case-sensitive) values are:

<code>SinglePage</code>	Display one page at a time
<code>OneColumn</code>	Display the pages in one column
<code>TwoColumnLeft</code>	Display the pages in two columns, odd numbered pages on the left
<code>TwoColumnRight</code>	Display the pages in two columns, even numbered pages on the left
<code>TwoPageLeft</code>	(PDF 1.5 and above) Display the pages two at a time, odd numbered pages on the left
<code>TwoPageRight</code>	(PDF 1.5 and above) Display the pages two at a time, even numbered pages on the left

For instance:

```
cpdf -set-page-layout TwoColumnRight in.pdf -o out.pdf
```

NB: If the file has a valid `/OpenAction` setting, which tells the PDF reader to open at a certain page or position on a page, this will override the page layout option. To prevent this, use the `-remove-dict-entry` functionality from Section 15.9:

```
cpdf -remove-dict-entry /OpenAction in.pdf -o out.pdf
```

11.5.2 Page Mode

The *page mode* in a PDF file defines how a viewer should display the document when first opened. The possible (case-sensitive) values are:

<code>UseNone</code>	Neither document outline nor thumbnail images visible
<code>UseOutlines</code>	Document outline (bookmarks) visible
<code>UseThumbs</code>	Thumbnail images visible
<code>FullScreen</code>	Full-screen mode (no menu bar, window controls, or anything but the document visible)
<code>UseOC</code>	(PDF 1.5 and above) Optional content group panel visible
<code>UseAttachments</code>	(PDF 1.5 and above) Attachments panel visible

For instance:

```
cpdf -set-page-mode FullScreen in.pdf -o out.pdf
```

11.5.3 Display Options

<code>-hide-toolbar</code>	Hide the viewer's toolbar
<code>-hide-menubar</code>	Document outline (bookmarks) visible
<code>-hide-window-ui</code>	Hide the viewer's scroll bars
<code>-fit-window</code>	Resize the document's windows to fit size of first page
<code>-center-window</code>	Position the document window in the center of the screen
<code>-display-doc-title</code>	Display the document title instead of the file name in the title bar

For instance:

```
cpdf -hide-toolbar true in.pdf -o out.pdf
```

The page a PDF file opens at can be set using `-open-at-page`:

```
cpdf -open-at-page 15 in.pdf -o out.pdf
```

To have that page scaled to fit the window in the viewer, use `-open-at-page-fit` instead:

```
cpdf -open-at-page-fit end in.pdf -o out.pdf
```

(Here, we used `end` to open at the last page. Any page specification describing a single page is ok here.)

11.6 Page Labels

It is possible to add *page labels* to a document. These are not the printed on the page, but may be displayed alongside thumbnails or in print dialogue boxes by PDF readers. We use `-add-page-labels` to do this, by default with decimal arabic numbers (1,2,3...). We can add `-label-style` to choose what type of labels to add from these kinds:

DecimalArabic	1,2,3,4,5...
LowercaseRoman	i,ii,iii,iv,v...
UppercaseRoman	I,II,III,IV,V...
LowercaseLetters	a,b,c,...,z,aa,bb...
UppercaseLetters	A,B,C,...,Z,AA,BB...
NoLabelPrefixOnly	No number, but a prefix will be used if defined.

We can use `-label-prefix` to add a textual prefix to each label. Consider a file with twenty pages and no current page labels (a PDF reader will assume 1,2,3... if there are none). We will add the following page labels:

i, ii, iii, iv, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, A-0, A-1, A-2, A-3, A-4, A-5

Here are the commands, in order:

```
cpdf -add-page-labels in.pdf 1-4 -label-style LowercaseRoman
-o out.pdf

cpdf -add-page-labels out.pdf 5-14 -o out.pdf

cpdf -add-page-labels out.pdf 15-20 -label-prefix "A-"
-label-startval 0 -o out.pdf
```

By default the labels begin at page number 1 for each range. To override this, we can use `-label-startval` (we used 0 in the final command), where we want the numbers to begin at zero rather than one. The option `-labels-progress` can be added to make sure the start value progresses between sub-ranges when the page range specified is disjoint, e.g 1-9, 30-40 or odd.

Page labels may be removed altogether by using `-remove-page-labels` command. To print the page labels from an existing file, use `-print-page-labels`. For example:

```
$ cpdf -print-page-labels cpdfmanual.pdf
labelstyle: LowercaseRoman
labelprefix: None
startpage: 1
startvalue: 1
labelstyle: DecimalArabic
labelprefix: None
startpage: 9
startvalue: 1
```


Chapter 12

File Attachments

```
cpdf -attach-file <filename> [-to-page <page number>] in.pdf -o out.pdf
cpdf -list-attached-files in.pdf
cpdf -remove-files in.pdf -o out.pdf
cpdf -dump-attachments in.pdf -o <directory>
```

PDF supports adding attachments (files of any kind, including other PDFs) to an existing file. The `cpdf` tool supports adding and removing *document-level attachments* — that is, ones which are associated with the document as a whole rather than with an individual page, and also *page-level attachments*, associated with a particular page.

12.1 Adding Attachments

To add an attachment, use the `-attach-file` operation. For instance,

```
cpdf -attach-file sheet.xls in.pdf -o out.pdf
```

attaches the Excel spreadsheet `sheet.xls` to the input file. If the file already has attachments, the new file is added to their number. You can specify multiple files to be attached by using `-attach-file` multiple times. They will be attached in the given order.

The `-to-page` option can be used to specify that the files will be attached to the given page, rather than at the document level. The `-to-page` option may be specified at most once.

12.2 Listing Attachments

To list all document- and page-level attachments, use the `-list-attached-files` operation. The page number and filename of each attachment is given, page 0 representing a document-level attachment.

```
$cpdf -list-attached-files 14psfonts.pdf
0 utility.ml
0 utility.mli
4 notes.xls
```

12.3 Removing Attachments

To remove all document-level and page-level attachments from a file, use the `-remove-files` operation:

```
cpdf -remove-files in.pdf -o out.pdf
```

12.4 Dumping Attachments to File

The `-dump-attachments` operation, when given a PDF file and a directory path as the output, will write each attachment under its filename (as displayed by `-list-attached-files` to that directory). The directory must exist prior to the call.

```
cpdf -dump-attachments in.pdf -o /home/fred/attachments
```

Unless the `-raw` option is given, the filenames are stripped of dubious special characters before writing. It is converted from unicode to 7 bit ASCII, and the following characters are removed, in addition to any character with ASCII code less than 32:

```
/ ? < > \ : * | " ^ + =
```

Chapter 13

Working with Images

```
cpdf -image-resolution <minimum resolution> in.pdf [<range>]
```

13.1 Detecting Low-resolution Images

To list all images in the given range of pages which fall below a given resolution (in dots-per-inch), use the `-image-resolution` function:

```
cpdf -image-resolution 300 in.pdf [<range>]
```

```
2, /Im5, 531, 684, 149.935297, 150.138267
2, /Im6, 184, 164, 149.999988, 150.458710
2, /Im7, 171, 156, 149.999996, 150.579145
2, /Im9, 65, 91, 149.999986, 151.071856
2, /Im10, 94, 60, 149.999990, 152.284285
2, /Im15, 184, 139, 149.960011, 150.672060
4, /Im29, 53, 48, 149.970749, 151.616446
```

The format is *page number, image name, x pixels, y pixels, x resolution, y resolution*. The resolutions refer to the image's effective resolution at point of use (taking account of scaling, rotation etc).

13.2 Removing an Image

To remove a particular image, find its name using `-image-resolution` with a sufficiently high resolution (so as to list all images), and then apply the `-draft` and `-draft-remove-only` operations from Section 15.1.

Chapter 14

Fonts

```
cpdf -list-fonts in.pdf
cpdf -copy-font fromfile.pdf -copy-font-page <int>
    -copy-font-name <name> in.pdf [<range>] -o out.pdf
cpdf -remove-fonts in.pdf -o out.pdf
cpdf -missing-fonts in.pdf
cpdf -embed-missing-fonts -gs <path to gs> in.pdf -o out.pdf
```

14.1 Listing Fonts

The `-list-fonts` operation prints the fonts in the document, one-per-line to standard output. For example:

```
1 /F245 /Type0 /Cleargothic-Bold /Identity-H
1 /F247 /Type0 /ClearGothicSerialLight /Identity-H
1 /F248 /Type1 /Times-Roman /WinAnsiEncoding
1 /F250 /Type0 /Cleargothic-RegularItalic /Identity-H
2 /F13 /Type0 /Cleargothic-Bold /Identity-H
2 /F16 /Type0 /Arial-ItalicMT /Identity-H
2 /F21 /Type0 /ArialMT /Identity-H
2 /F58 /Type1 /Times-Roman /WinAnsiEncoding
2 /F59 /Type0 /ClearGothicSerialLight /Identity-H
2 /F61 /Type0 /Cleargothic-BoldItalic /Identity-H
2 /F68 /Type0 /Cleargothic-RegularItalic /Identity-H
3 /F47 /Type0 /Cleargothic-Bold /Identity-H
3 /F49 /Type0 /ClearGothicSerialLight /Identity-H
3 /F50 /Type1 /Times-Roman /WinAnsiEncoding
3 /F52 /Type0 /Cleargothic-BoldItalic /Identity-H
3 /F54 /Type0 /TimesNewRomanPS-BoldItalicMT /Identity-H
3 /F57 /Type0 /Cleargothic-RegularItalic /Identity-H
```

```
4 /F449 /Type0 /ClearGothic-Bold /Identity-H
4 /F451 /Type0 /ClearGothicSerialLight /Identity-H
4 /F452 /Type1 /Times-Roman /WinAnsiEncoding
```

The first column gives the page number, the second the internal unique font name, the third the type of font (Type1, TrueType etc), the fourth the PDF font name, the fifth the PDF font encoding.

14.2 Copying Fonts

In order to use a font other than the standard 14 with `-add-text`, it must be added to the file. The font source PDF is given, together with the font's resource name on a given page, and that font is copied to all the pages in the input file's range, and then written to the output file.

The font is named in the output file with its basefont name, so it can be easily used with `-add-text`.

For example, if the file `fromfile.pdf` has a font `/GHLIGA+c128` with the name `/F10` on page 1 (this information can be found with `-list-fonts`), the following would copy the font to the file `in.pdf` on all pages, writing the output to `out.pdf`:

```
cpdf -copy-font fromfile.pdf -copy-font-name /F10
    -copy-font-page 1 in.pdf -o out.pdf
```

Text in this font can then be added by giving `-font /GHLIGA+c128`. Be aware that due to the vagaries of PDF font handling concerning which characters are present in the source font, not all characters may be available, or the encoding (mapping from input codes to glyphs) may be non-obvious.

14.3 Removing Fonts

To remove embedded fonts from a document, use `-remove-fonts`. PDF readers will substitute local fonts for the missing fonts. The use of this function is only recommended when file size is the sole consideration.

```
cpdf -remove-fonts in.pdf -o out.pdf
```

14.4 Missing Fonts

The `-missing-fonts` operation lists any unembedded fonts in the document, one per line.

```
cpdf -missing-fonts in.pdf
```

The format is

```
Page number, Name, Subtype, Basefont, Encoding
```

The operation `-embed-missing-fonts` will process the file with `gs` (which must be installed) to embed missing fonts (where found):

```
cpdf -embed-missing-fonts -gs gs in.pdf -o out.pdf
```


Chapter 15

Miscellaneous

```
cpdf -draft [-boxes] [-draft-remove-only <n>] in.pdf [<range>] -o out.pdf
cpdf -remove-all-text in.pdf [<range>] -o out.pdf
cpdf -blacktext in.pdf [<range>] -o out.pdf
cpdf -blacklines in.pdf [<range>] -o out.pdf
cpdf -blackfills in.pdf [<range>] -o out.pdf
cpdf -thinline <minimum thickness> in.pdf [<range>] -o out.pdf
cpdf -clean in.pdf -o out.pdf
cpdf -set-version <version number> in.pdf -o out.pdf
cpdf -copy-id-from source.pdf in.pdf -o out.pdf
cpdf -remove-id in.pdf -o out.pdf
cpdf -list-spot-colors in.pdf
cpdf -remove-dict-entry <dictionary key> in.pdf -o out.pdf
cpdf -remove-clipping [<range>] in.pdf -o out.pdf
```

15.1 Draft Documents

The `-draft` operation removes bitmap (photographic) images from a file, so that it can be printed with less ink. Optionally, the `-boxes` option can be added, filling the spaces left blank with a crossed box denoting where the image was. This is not guaranteed to be fully visible in all cases (the bitmap may have been partially covered by vector objects or clipped in the original). For example:

```
cpdf -draft -boxes in.pdf -o out.pdf
```

To remove a single image only, specify `-draft-remove-only`, giving the name of the image obtained by a call to `-image-resolution` as described in Section 13.1 and giving the appropriate page. For example:

```
cpdf -draft -boxes -draft-remove-only "/Im1" in.pdf 7 -o out.pdf
```

To remove text instead of images, use the `-remove-all-text` operation:

```
cpdf -remove-all-text in.pdf -o out.pdf
```

15.2 Blackening Text, Lines and Fills

Sometimes PDF output from an application (for instance, a web browser) has text in colors which would not print well on a grayscale printer. The `-blacktext` operation blackens all text on the given pages so it will be readable when printed.

This will not work on text which has been converted to outlines, nor on text which is part of a form.

```
cpdf -blacktext in.pdf -o out.pdf
```

The `-blacklines` operation blackens all lines on the given pages.

```
cpdf -blacklines in.pdf -o out.pdf
```

The `-blackfills` operation blackens all fills on the given pages.

```
cpdf -blackfills in.pdf -o out.pdf
```

Contrary to their names, all these operations can use another color, if specified with `-color`.

15.3 Hairline Removal

Quite often, applications will use very thin lines, or even the value of 0, which in PDF means "The thinnest possible line on the output device". This might be fine for on-screen work, but when printed on a high resolution device, such as by a commercial printer, they may be too faint, or disappear altogether. The `-thinline` operation prevents this by changing all lines thinner than `<minimal thickness>` to the given thickness. For example:

```
cpdf -thinline 0.2mm in.pdf [<range>] -o out.pdf
```

Thicken all lines less than 0.2mm to that value.

15.4 Garbage Collection

Sometimes incremental updates to a file by an application, or bad applications can leave data in a PDF file which is no longer used. This function removes that unneeded data.

```
cpdf -clean in.pdf -o out.pdf
```

15.5 Change PDF Version Number

To change the pdf version number, use the `-set-version` operation, giving the part of the version number after the decimal point. For example:

```
cpdf -set-version 4 in.pdf -o out.pdf
```

Change file to PDF 1.4.

This does not alter any of the actual data in the file — just the supposed version number. For PDF versions starting with 2 add ten to the number. For example, for PDF version 2.0, use `-set-version 10`.

15.6 Copy ID

The `-copy-id-from` operation copies the ID from the given file to the input, writing to the output.

```
cpdf -copy-id-from source.pdf in.pdf -o out.pdf
```

Copy the id from `source.pdf` to the contents of `in.pdf`, writing to `out.pdf`.

If there is no ID in the source file, the existing ID is retained. You cannot use `-recrypt` with `-copy-id-from`.

15.7 Remove ID

The `-remove-id` operation removes the ID from a document.

```
cpdf -remove-id in.pdf -o out.pdf
```

Remove the ID from `in.pdf`, writing to `out.pdf`.

You cannot use `-recrypt` with `-remove-id`.

15.8 List Spot Colours

This operation lists the name of any “separation” color space in the given PDF file.

```
cpdf -list-spot-colors in.pdf
```

List the spot colors, one per line in `in.pdf`, writing to `stdout`.

15.9 Removing Dictionary Entries

This is for editing data within the PDF’s internal representation. Use with caution.

```
cpdf -remove-dict-entry /One in.pdf -o out.pdf
```

Remove the entry for `/One` in every dictionary in `in.pdf`, writing to `out.pdf`.

15.10 Removing Clipping

The `-remove-clipping` operation removes any clipping paths on given pages from the file.

```
cpdf -remove-clipping in.pdf -o out.pdf
```

Remove clipping paths in `in.pdf`, writing to `out.pdf`.

Appendix A

Dates

A.1 PDF Date Format

Dates in PDF are specified according to the following format:

`D : YYYYMMDDHHmmSSOHH 'mm '`

where:

- YYYY is the year;
- MM is the month;
- DD is the day (01-31);
- HH is the hour (00-23);
- mm is the minute (00-59);
- SS is the second (00-59);
- O is the relationship of local time to Universal Time (UT), denoted by '+', '-' or 'Z';
- HH is the absolute value of the offset from UT in hours (00-23);
- mm is the absolute value of the offset from UT in minutes (00-59).

A contiguous prefix of the parts above can be used instead, for lower accuracy dates. For example:

`D : 2014 (2014)`

`D : 20140103 (3rd January 2014)`

D:201401031854-08'00' (3rd January 2014, 6:54PM, US Pacific Standard Time)

A.2 XMP Metadata Date Format

These are the possible data formats for `-set-metadata-date`:

YYYY
YYYY-MM
YYYY-MM-DD
YYYY-MM-DDThh:mmTZD
YYYY-MM-DDThh:mm:ssTZD

where:

YYYY	year
MM	month (01 = Jan)
DD	day of month (01 to 31)
hh	hour (00 to 23)
mm	minute (00 to 59)
ss	second (00 to 59)
TZD	time zone designator (Z or +hh:mm or -hh:mm)

Index

- AND, 4
- annotations
 - copying, 41
 - listing, 41
 - removing, 42
- attachments, 51
 - adding, 51
 - dumping to file, 52
 - listing, 51
 - removing, 52
- bates numbers, 33
- blacken
 - fills, 60
 - lines, 60
 - text, 60
- blank pages
 - inserting, 39
- bookmarks, 25
 - adding, 27
 - listing, 25
 - opening at level, 27
 - removing, 27
- color, 35
- compressing, 23
- control file, 9
- create new PDF, 10
- creator, 5
- crop pages, 18
- date, 32
 - defined, 63
- decompressing, 23
- decryption, 3, 21
- document information, 43
- document outline, 25
- draft, 59
- encryption, 13, 21
- error handling, 9
- file ID, 6
 - copy, 61
 - remove, 61
- flip pages, 18
- font, 34
 - embedding, 10
 - listing, 55
- garbage collection, 61
- hairline removal, 60
- input files, 1
- input range, 2
- linearization, 6
- malformed file, 7
- media box, 18
- merging, 11
- metadata, 43
 - XMP, 46
- object stream, 7
- outline text, 36
- output files, 1
- owner password, 3
- page
 - labels, 48
 - layout, 47
 - mode, 47
 - numbers, 33
 - range, 2
 - size, 16
- password, 3

Coherent PDF Library (libcpdf)

Developer's Manual

Version 2.2 (January 2017)



Coherent Graphics Ltd

For bug reports, feature requests and comments, email
contact@coherentgraphics.co.uk

©2017 Coherent Graphics Limited. All rights reserved.

Adobe, Acrobat, Adobe PDF, Adobe Reader and PostScript are registered trademarks of Adobe Systems Incorporated. Windows is a registered trademarks of Microsoft Corporation.

Contents

Contents	iii
0 Preliminaries	5
1 Basics	7
2 Merging and Splitting	13
3 Pages	15
4 Encryption	19
5 Compression	21
6 Bookmarks	23
7 Presentations	25
8 Logos, Watermarks and Stamps	27
9 Multipage Facilities	31
10 Annotations	33
11 Document Information and Metadata	35
12 File Attachments	41
13 Images	43
14 Fonts	45
15 Miscellaneous	47
A Dates	49
B Example Program in C	51

Note

The chapters are numbered to be the same as those in the manual for the Coherent PDF Command Line Tools (cpdfmanual.pdf). However, some of the content has moved where circumstances dictate – for example, encryption is wholly described in Chapter 1 rather than Chapter 4.

All functions in cpdflib take or return UTF8 text - the command line tool's other modes, "Raw" and "Stripped" are not supported.

Installation

The Coherent PDF Library is provided either in compiled form (the archive file `libcpdf.a` and the library header `cpdfplibwrapper.h`), or as source code. Instructions for building from source are included in the distribution.

Linux, Unix and OS/X Place `libcpdf.a`, `libbigarray.a` and `libunix.a` somewhere suitable. Instruct your C linker to link with them. Place `cpdfplibwrapper.h` somewhere suitable and instruct your C compiler to search for headers there. The library is now ready for use.

Microsoft Windows Place `libcpdf.dll` somewhere suitable and instruct your C compiler to link with it. Place `cpdfplibwrapper.h` somewhere suitable and instruct your C compiler to search for headers there. The library is now ready for use.

0 Preliminaries

/ A C wrapper to cpdf PDF tools library. Free for non-commercial use. See LICENSE for details. To purchase a license, please visit <http://www.coherentpdf.com/>*

*Text arguments and results are in UTF8. */*

/ CHAPTER 0. Preliminaries */*

/ The function cpdf_startup(argv) must be called before using the library. */*
void cpdf_startup (**char** **);

/ Return the version of the cpdflib library as a string */*
char *cpdf_version ();

/ Some operations have a fast mode. The default is 'slow' mode, which works
* even on old-fashioned files. For more details, see section 1.13 of the CPDF
* manual. These functions set the mode globally. */*
void cpdf_setFast ();
void cpdf_setSlow ();

/ Undocumented. */*
void cpdf_setDemo (**int**);

/ Errors. cpdf_lastError and cpdf_lastErrorString hold information about the
* last error to have occurred. They should be consulted after each call. If
* cpdf_lastError is non-zero, there was an error, and cpdf_lastErrorString
* gives details. If cpdf_lastError is zero, there was no error on the most
* recent cpdf call. */*
extern int cpdf_lastError;
extern char *cpdf_lastErrorString;

/ cpdf_clearError clears the current error state. */*
void cpdf_clearError (**void**);

/ cpdf_onExit is a debug function which prints some information about
* resource usage. This can be used to detect if PDFs or ranges are being
* deallocated properly. */*
void cpdf_onExit (**void**);

1 Basics

```
/* CHAPTER 1. Basics */

/* cpdf_fromFile(filename, userpw) loads a PDF file from a given file. Supply a
 * user password (possibly blank) in case the file is encrypted. It won't be
 * decrypted, but sometimes the password is needed just to load the file. */
int cpdf_fromFile (const char[], const char[]);

/* cpdf_fromFileLazy(pdf, userpw) loads a PDF from a file, doing only minimal
 * parsing. The objects will be read and parsed when they are actually needed.
 * Use this when the whole file won't be required. Also supply a user password
 * (possibly blank) in case the file is encrypted. It won't be decrypted, but
 * sometimes the password is needed just to load the file. */
int cpdf_fromFileLazy (const char[], const char[]);

/* cpdf_fromMemory(data, length, userpw) loads a file from memory, given a
 * pointer and a length, and the user password. */
int cpdf_fromMemory (void *, int, const char[]);

/* cpdf_fromMemory(data, length, userpw) loads a file from memory, given a
 * pointer and a length, and the user password, but lazily like
 * cpdf_fromFileLazy. */
int cpdf_fromMemoryLazy (void *, int, const char[]);

/* cpdf_blankDocument(width, height, num_pages) creates a blank document with
 * pages of the given width (in points), height (in points), and number of
 * pages. */
int cpdf_blankDocument (double, double, int);

/* Standard page sizes. */
enum cpdf_papersize
{
    cpdf_a0portrait, /* A0 portrait */
    cpdf_a1portrait, /* A1 portrait */
    cpdf_a2portrait, /* A2 portrait */
    cpdf_a3portrait, /* A3 portrait */
    cpdf_a4portrait, /* A4 portrait */
    cpdf_a5portrait, /* A5 portrait */
    cpdf_a0landscape, /* A0 landscape */
    cpdf_a1landscape, /* A1 landscape */
    cpdf_a2landscape, /* A2 landscape */
    cpdf_a3landscape, /* A3 landscape */
    cpdf_a4landscape, /* A4 landscape */
}
```

1. BASICS

```
    cpdf_a5landscape, /* A5 landscape */
    cpdf_usletterportrait, /* US Letter portrait */
    cpdf_usletterlandscape, /* US Letter landscape */
    cpdf_uslegalportrait, /* US Legal portrait */
    cpdf_uslegallandscape /* US Legal landscape */
};

/* cpdf_blankDocumentPaper(papersize, num_pages) makes a blank document given a
 * page size and number of pages. */
int cpdf_blankDocumentPaper (enum cpdf_papersize, int);

/* Remove a PDF from memory, given its number. */
void cpdf_deletePdf (int);

/* Calling cpdf_replacePdf(a, b) places PDF b under number a. Original a and b are
 * no longer available. */
void cpdf_replacePdf (int, int);

/* To enumerate the list of currently allocated PDFs, call
 * cpdf_startEnumeratePDFs which gives the number, n, of PDFs allocated, then
 * cpdf_enumeratePDFsInfo and cpdf_enumeratePDFsKey with index numbers from
 * 0...(n - 1). Call cpdf_endEnumeratePDFs to clean up. */
int cpdf_startEnumeratePDFs (void);
int cpdf_enumeratePDFsKey (int);
char *cpdf_enumeratePDFsInfo (int);
void cpdf_endEnumeratePDFs (void);

/* Convert a figure in centimetres to points (72 points to 1 inch) */
double cpdf_ptOfCm (double);

/* Convert a figure in millimetres to points (72 points to 1 inch) */
double cpdf_ptOfMm (double);

/* Convert a figure in inches to points (72 points to 1 inch) */
double cpdf_ptOfIn (double);

/* Convert a figure in points to centimetres (72 points to 1 inch) */
double cpdf_cmOfPt (double);

/* Convert a figure in points to millimetres (72 points to 1 inch) */
double cpdf_mmOfPt (double);

/* Convert a figure in points to inches (72 points to 1 inch) */
double cpdf_inOfPt (double);

/* A page range is a list of page numbers used to restrict operations to
 * certain pages. A page specification is a textual description of a page
 * range, such as "1-12,18-end". Here is the syntax:
 *
 * o A dash (-) defines ranges, e.g. 1-5 or 6-3.
 *
 * o A comma (,) allows one to specify several ranges, e.g. 1-2,4-5.
 *
 * o The word end represents the last page number.
```

```

*
* o The words odd and even can be used in place of or at the end of a page
* range to restrict to just the odd or even pages.
*
* o The words portrait and landscape can be used in place of or at the end
* of a page range to restrict to just those pages which are portrait or
* landscape. Note that the meaning of "portrait" and "landscape" does not
* take account of any viewing rotation in place (use cpdf_upright first, if
* required). A page with equal width and height is considered neither
* portrait nor landscape.
*
* o The word reverse is the same as end-1.
*
* o The word all is the same as 1-end.
*
* o A range must contain no spaces.
*
* o A tilde (~) defines a page number counting from the end of the document
* rather than the beginning. Page ~1 is the last page, ~2 the
* penultimate page etc. */

/* cpdf_parsePagespec(pdf, range) parses a page specification with reference to
* a given PDF (the PDF is supplied so that page ranges which reference pages
* which do not exist are rejected). */
int cpdf_parsePagespec (int, const char[]);

/* cpdf_validatePagespec(range) validates a page specification so far as is
* possible in the absence of the actual document */
int cpdf_validatePagespec (const char[]);

/* cpdf_stringOfPagespec(pdf, range) builds a page specification from a page
* range. For example, the range containing 1,2,3,6,7,8 in a document of 8
* pages might yield "1-3,6-end" */
char *cpdf_stringOfPagespec (int, int);

/* cpdf_blankRange() creates a range with no pages in. */
int cpdf_blankRange (void);

/* cpdf_deleteRange(range) deletes a range. */
void cpdf_deleteRange (int);

/* cpdf_range(from, to) build a range from one page to another inclusive. For example,
* cpdf_range(3,7) gives the range 3,4,5,6,7 */
int cpdf_range (int, int);

/* cpdf_all(pdf) is the range containing all the pages in a given document. */
int cpdf_all (int);

/* cpdf_even(range) makes a range which contains just the even pages of another
* range */
int cpdf_even (int);

/* cpdf_odd(range) makes a range which contains just the odd pages of another
* range */

```

1. BASICS

```
int cpdf_odd (int);

/* cpdf_rangeUnion(a, b) makes the union of two ranges giving a range containing t.
 * pages in range a and range b. */
int cpdf_rangeUnion (int, int);

/* cpdf_difference(a, b) makes the difference of two ranges, giving a range
 * containing all the pages in a except for those which are also in b. */
int cpdf_difference (int, int);

/* cpdf_removeDuplicates(range) deduplicates a range, making a new one. */
int cpdf_removeDuplicates (int);

/* cpdf_rangeLength gives the number of pages in a range. */
int cpdf_rangeLength (int);

/* cpdf_rangeGet(range, n) gets the page number at position n in a range, where
 * n runs from 0 to rangeLength - 1. */
int cpdf_rangeGet (int, int);

/* cpdf_rangeAdd(range, page) adds the page to a range, if it is not already
 * there. */
int cpdf_rangeAdd (int, int);

/* cpdf_isInRange(range, page) returns true if the page is in the range, false
 * otherwise. */
int cpdf_isInRange (int, int);

/* cpdf_pages(pdf) returns the number of pages in a PDF. */
int cpdf_pages (int);

/* cpdf_pagesFast(password, filename) returns the number of pages in a given
 * PDF, with given user encryption password. It tries to do this as fast as
 * possible, without loading the whole file. */
int cpdf_pagesFast (const char[], const char[]);

/* cpdf_toFile (pdf, filename, linearize, make_id) writes the file to a given
 * filename. If linearize is true, it will be linearized. If make_id is true,
 * it will be given a new ID. */
void cpdf_toFile (int, const char[], int, int);

/* cpdf_toFile (pdf, filename, linearize, make_id, preserve_objstm,
 * generate_objstm, compress_objstm) writes the file to a given filename. If
 * make_id is true, it will be given a new ID. If preserve_objstm is true,
 * existing object streams will be preserved. If generate_objstm is true,
 * object streams will be generated even if not originally present. If
 * compress_objstm is true, object streams will be compressed (what we usually
 * want). WARNING: the pdf argument will be invalid after this call, and should
 * be discarded. */
void cpdf_toFileExt (int, const char[], int, int, int, int, int);

/* Given a buffer of the correct size, cpdf_toFileMemory (pdf, linearize,
 * make_id, &length) writes it and returns the buffer. The buffer length is
 * filled in &length. */
```

```

void *cpdf_toMemory (int, int, int, int *);

/* cpdf_isEncrypted(pdf) returns true if a document is encrypted, false otherwise. */
int cpdf_isEncrypted (int);

/* Given a filename, is a PDF linearized? */
int is_linearized (const char[]);

/* cpdf_decryptPdf(pdf, userpw) attempts to decrypt a PDF using the given user
 * password. The error code is non-zero if the decryption fails. */
void cpdf_decryptPdf (int, const char[]);

/* cpdf_decryptPdfOwner(pdf, ownerpw) attempts to decrypt a PDF using the given
 * owner password. The error code is non-zero if the decryption fails. */
void cpdf_decryptPdfOwner (int, const char[]);

/* File permissions. These are inverted, in the sense that the presence of
 * one of them indicates a restriction. */
enum cpdf_permission
{
    cpdf_noEdit, /* Cannot edit the document */
    cpdf_noPrint, /* Cannot print the document */
    cpdf_noCopy, /* Cannot copy the document */
    cpdf_noAnnot, /* Cannot annotate the document */
    cpdf_noForms, /* Cannot edit forms in the document */
    cpdf_noExtract, /* Cannot extract information */
    cpdf_noAssemble, /* Cannot assemble into a bigger document */
    cpdf_noHqPrint /* Cannot print high quality */
};

/* Encryption methods. Suffixes 'false' and 'true' indicates lack of or
 * presence of encryption for XMP metadata streams. */
enum cpdf_encryptionMethod
{
    cpdf_pdf40bit, /* 40 bit RC4 encryption */
    cpdf_pdf128bit, /* 128 bit RC4 encryption */
    cpdf_aes128bitfalse, /* 128 bit AES encryption, do not encrypt metadata. */
    cpdf_aes128bittrue, /* 128 bit AES encryption, encrypt metadata */
    cpdf_aes256bitfalse, /* Deprecated. Do not use for new files */
    cpdf_aes256bittrue, /* Deprecated. Do not use for new files */
    cpdf_aes256bitisofalse, /* 256 bit AES encryption, do not encrypt metadata. */
    cpdf_aes256bitisotrue /* 256 bit AES encryption, encrypt metadata */
};

/* cpdf_toFileEncrypted(pdf, encryption_method, permissions, permission_length,
 * owner_password, user password, linearize, makeid) writes a file as
 * encrypted. */
void cpdf_toFileEncrypted
    (int, int, int *, int, const char[], const char[], int, int, const char[]);

/* cpdf_toFileEncryptedExt(pdf, encryption_method, permissions,
 * permission_length, owner_password, user_password, linearize, makeid,
 * preserve_objstm, generate_objstm, compress_objstm, filename) WARNING: the
 * pdf argument will be invalid after this call, and should be discarded. */

```

1. BASICS

```
void cpdf_toFileEncryptedExt
(int, int, int *, int, const char[], const char[], int, int, int, int,
const char[]);

/* cpdf_hasPermission(pdf, permission) returns true if the given permission
 * (restriction) is present. */
int cpdf_hasPermission (int, enum cpdf_permission);

/* cpdf_encryptionMethod(pdf) return the encryption method currently in use on
 * a document. */
enum cpdf_encryptionMethod cpdf_encryptionKind (int);

/* Encryption and Permission status */

/* Internal status of a pdf loaded by the library. This is data kept separate
 * from the actual PDF. */
enum cpdf_pdfStatus
{
    cpdf_notEncrypted,
    cpdf_encrypted,
    cpdf_wasDecryptedWithUser,
    cpdf_wasDecryptedWithOwner
};

/* cpdf_lookupPdfStatus(pdf) returns the encryption status of a PDF. */
enum cpdf_pdfStatus cpdf_lookupPdfStatus (int);

/* cpdf_hasPermissionStatus(pdf, permission) returns true if the PDF has or had
 * the permission given set, assuming it is or was encrypted? */
int cpdf_hasPermissionStatus (int, enum cpdf_permission);

/* cpdf_encryptionMethod(pdf) returns what is (or was) the encryption method? */
enum cpdf_encryptionMethod cpdf_lookupPdfEncryption (int);

/* cpdf_lookupPdfUserPassword(pdf) finds the user password which was used to
 * decrypt a PDF, if it has status cpdf_wasDecryptedWithUser */
char *cpdf_lookupPdfUserPassword (int);
```

2 Merging and Splitting

```
/* CHAPTER 2. Merging and Splitting */

/* cpdf_mergeSimple(pdfs, length) given an array of PDFs, and its length,
* merges the files into a new one, which is returned. */
int cpdf_mergeSimple (int *, int);

/* cpdf_merge(pdfs, len, retain_numbering, remove_duplicate_fonts) merges
* the PDFs. If retain_numbering is true page labels are not rewritten. If
* remove_duplicate_fonts is true, duplicate fonts are merged. This is useful
* when the source documents for merging originate from the same source. */
int cpdf_merge (int *, int, int, int);

/* cpdf_mergeSame(pdfs, len, retain_numbering, remove_duplicate_fonts, ranges)
* is the same as cpdf_merge, except that it has an additional argument
* - an array of page ranges. This is used to select the pages to pick from
* each PDF. This avoids duplication of information when multiple discrete
* parts of a source PDF are included. */
int cpdf_mergeSame (int *, int, int, int, int *);

/* cpdf_selectPages(pdf, range) returns a new document which just those pages
* in the page range. */
int cpdf_selectPages (int, int);
```

3 Pages

```
/* CHAPTER 3. Pages */

/* cpdf_scalePages(pdf, range, x scale, y scale) scales the page dimensions
 * and content by the given scale, about (0, 0). Other boxes (crop etc. are
 * altered as appropriate) */
void cpdf_scalePages (int, int, double, double);

/* cpdf_scaleToFit(pdf, range, width height, scale) scales the content to fit
 * new page dimensions (width x height) multiplied by scale (typically 1.0).
 * Other boxed (crop etc. are altered as appropriate) */
void cpdf_scaleToFit (int, int, double, double, double);

/* cpdf_scaleToFitPaper(pdf, range, papersize, scale) scales the page content
 * to fit the given page size, possibly multiplied by scale (typically 1.0) */
void cpdf_scaleToFitPaper (int, int, enum cpdf_papersize, double);

/* Positions on the page. Used for scaling about a point, and adding text. */
enum cpdf_anchor
{
    cpdf_posCentre, /* Absolute centre */
    cpdf_posLeft, /* Absolute left */
    cpdf_posRight, /* Absolute right */
    cpdf_top, /* Top top centre of the page */
    cpdf_topLeft, /* The top left of the page */
    cpdf_topRight, /* The top right of the page */
    cpdf_left, /* The left hand side of the page, halfway down */
    cpdf_bottomLeft, /* The bottom left of the page */
    cpdf_bottom, /* The bottom middle of the page */
    cpdf_bottomRight, /* The bottom right of the page */
    cpdf_right, /* The right hand side of the page, halfway down */
    cpdf_diagonal, /* Diagonal, bottom left to top right */
    cpdf_reverseDiagonal /* Diagonal, top left to bottom right */
};

/* A cpdf_position is an anchor (above) and zero or one or two parameters
 * (cpdf_coord1, cpdf_coord2).
 *
 * cpdf_posCentre: Two parameters, x and y
 * cpdf_posLeft: Two parameters, x and y
 * cpdf_posRight: Two parameters, x and y
 * cpdf_top: One parameter -- distance from top
 * cpdf_topLeft: One parameter -- distance from top left
```

3. PAGES

```
* cpdf_topRight: One parameter -- distance from top right
* cpdf_left: One parameter -- distance from left middle
* cpdf_bottomLeft: One parameter -- distance from bottom left
* cpdf_bottom: One parameter -- distance from bottom
* cpdf_bottomRight: One parameter -- distance from bottom right
* cpdf_right: One parameter -- distance from right
* cpdf_diagonal: Zero parameters
* cpdf_reverseDiagonal: Zero paremeters */
struct cpdf_position
{
    int cpdf_anchor; /* Position anchor */
    double cpdf_coord1; /* Parameter one */
    double cpdf_coord2; /* Parameter two */
};

/* cpdf_scaleContents(pdf, range, position, scale) scales the contents of the
 * pages in the range about the point given by the cpdf_position, by the
 * scale given. */
void cpdf_scaleContents (int, int, struct cpdf_position, double);

/* cpdf_shiftContents(pdf, range, dx, dy) shifts the content of the pages in
 * the range. */
void cpdf_shiftContents (int, int, double, double);

/* cpdf_rotate(pdf, range, rotation) changes the viewing rotation to an
 * absolute value. Appropriate rotations are 0, 90, 180, 270. */
void cpdf_rotate (int, int, int);

/* cpdf_rotateBy(pdf, range, rotation) changes the viewing rotation by a
 * given number of degrees. Appropriate values are 90, 180, 270. */
void cpdf_rotateBy (int, int, int);

/* cpdf_rotateContents(pdf, range, angle) rotates the content about the centre
 * of the page by the given number of degrees, in a clockwise direction. */
void cpdf_rotateContents (int, int, double);

/* cpdf_upright(pdf, range) changes the viewing rotation of the pages in the
 * range, counter-rotating the dimensions and content such that there is no
 * visual change. */
void cpdf_upright (int, int);

/* cpdf_hFlip(pdf, range) flips horizontally the pages in the range. */
void cpdf_hFlip (int, int);

/* cpdf_vFlip(pdf, range) flips vertically the pages in the range. */
void cpdf_vFlip (int, int);

/* cpdf_crop(pdf, range, x, y, w, h) crops a page, replacing any existing
 * crop box. The dimensions are in points. */
void cpdf_crop (int, int, double, double, double, double);

/* cpdf_removeCrop(pdf, range) removes any crop box from pages in the range. */
void cpdf_removeCrop (int, int);
```

```
/* cpdf_removeTrim(pdf, range) removes any crop box from pages in the range. */
void cpdf_removeTrim (int, int);

/* cpdf_removeArt(pdf, range) removes any crop box from pages in the range. */
void cpdf_removeArt (int, int);

/* cpdf_removeBleed(pdf, range) removes any crop box from pages in the range. */
void cpdf_removeBleed (int, int);

/* cpdf_trimMarks(pdf, range) adds trim marks to the given pages, if the trimbox exists. */
void cpdf_trimMarks (int, int);

/* cpdf_showBoxes(pdf, range) shows the boxes on the given pages, for debug. */
void cpdf_showBoxes (int, int);

/* cpdf_hardBox make a given box a 'hard box' i.e clips it explicitly. */
void cpdf_hardBox (int, int, const char[]);
```

4 Encryption

Covered in Chapter 1.

```
/* CHAPTER 4. Encryption */
```

```
/* Encryption covered under Chapter 1 in cpdflib. */
```

5 Compression

```
/* CHAPTER 5. Compression */

/* cpdf_compress(pdf) compresses any uncompressed streams in the given PDF
 * using the Flate algorithm. */
void cpdf_compress (int);

/* cpdf_uncompress(pdf) uncompresses any streams in the given PDF, so long as
 * the compression method is supported. */
void cpdf_decompress (int);

/* cpdf_squeeze(userpw, logfile, infile, outfile) squeezes a file on disk,
 * logging to logfile if given. */
int cpdf_squeeze (const char[], const char[], const char[], const char[]);

/* cpdf_squeezeToMemory(pdf) squeezes a pdf in memory. */
void cpdf_squeezeInMemory (int);
```

6 Bookmarks

```
/* CHAPTER 6. Bookmarks */

/* cpdf_startGetBookmarkInfo(pdf) start the bookmark retrieval process for a
 * given PDF. */
void cpdf_startGetBookmarkInfo (int);

/* cpdf_numberBookmarks gets the number of bookmarks for the PDF given to
 * cpdf_startGetBookmarkInfo. */
int cpdf_numberBookmarks (void);

/* cpdf_getBookmarkLevel(serial) get bookmark level for the given bookmark
 * (0...(n - 1)). */
int cpdf_getBookmarkLevel (int);

/* cpdf_getBookmarkPage gets the bookmark target page for the given PDF (which
 * must be the same as the PDF passed to cpdf_startSetBookmarkInfo) and
 * bookmark (0...(n - 1)). */
int cpdf_getBookmarkPage (int, int);

/* cpdf_getBookmarkText returns the text of bookmark (0...(n - 1)). */
char *cpdf_getBookmarkText (int);

/* cpdf_getBookmarkOpenStatus(pdf) is true if the bookmark is open. */
int cpdf_getBookmarkOpenStatus (int);

/* cpdf_endGetBookmarkInfo ends the bookmark retrieval process, cleaning up. */
void cpdf_endGetBookmarkInfo (void);

/* cpdf_startGetBookmarkInfo(n) start the bookmark setting process for n
 * bookmarks. */
void cpdf_startSetBookmarkInfo (int);

/* cpdf_setBookmarkLevel(n, level) set bookmark level for the given bookmark
 * (0...(n - 1)). */
void cpdf_setBookmarkLevel (int, int);

/* cpdf_setBookmarkPage(pdf, bookmark, targetpage) sets the bookmark target
 * page for the given PDF (which must be the same as the PDF to be passed to
 * cpdf_endSetBookmarkInfo) and bookmark (0...(n - 1)). */
void cpdf_setBookmarkPage (int, int, int);

/* cpdf_setBookmarkOpenStatus(n, status) set the open status of a bookmark,
```

6. BOOKMARKS

```
 * true or false. */
void cpdf_setBookmarkOpenStatus (int, int);

/* cpdf_setBookmarkText(n, text) sets the text of bookmark (0...(n - 1)). */
void cpdf_setBookmarkText (int, const char[]);

/* cpdf_endSetBookmarkInfo(pdf) end the bookmark setting process, writing the
 * bookmarks to the given PDF. */
void cpdf_endSetBookmarkInfo (int);
```

7 Presentations

Not supported by libcpdf. Use the command line tools instead.

/ CHAPTER 7. Presentations */*

/ Not included in the library version */*

8 Logos, Watermarks and Stamps

```
/* CHAPTER 8. Logos, Watermarks and Stamps */

/* cpdf_stampOn(stamp_pdf, pdf, range) stamps stamp_pdf on top of all the
 * pages in the document which are in the range. The stamp is placed with its
 * origin at the origin of the target document. */
void cpdf_stampOn (int, int, int);

/* cpdf_stampUnder(stamp_pdf, pdf, range) stamps stamp_pdf under all the pages
 * in the document which are in the range. The stamp is placed with its origin
 * at the origin of the target document. */
void cpdf_stampUnder (int, int, int);

/* cpdf_stampExtended(pdf, pdf2, range, isover, scale_stamp_to_fit, pos,
 * relative_to_cropbox) is a stamping function with extra features.
 * - isover true, pdf goes over pdf2, isover false, pdf goes under pdf2
 * - scale_stamp_to_fit scales the stamp to fit the page
 * - pos gives the position to put the stamp
 * - relative_to_cropbox: if true, pos is relative to cropbox not mediabox */
void cpdf_stampExtended (int, int, int, int, int, struct cpdf_position, int);

/* cpdf_combinePages(under, over) combines the PDFs page-by-page, putting
 * each page of 'over' over each page of 'under' */
int cpdf_combinePages (int, int);

/* Adding text. Adds text to a PDF, if the characters exist in the font. */

/* Special codes
 *
 * %Page Page number in arabic notation (1, 2, 3...)
 * %roman Page number in lower-case roman notation (i, ii, iii...)
 * %Roman Page number in upper-case roman notation (I, II, III...)
 * %EndPage Last page of document in arabic notation
 * %Label The page label of the page
 * %EndLabel The page label of the last page
 * %filename The full file name of the input document
 * %a Abbreviated weekday name (Sun, Mon etc.)
 * %A Full weekday name (Sunday, Monday etc.)
 * %b Abbreviated month name (Jan, Feb etc.)
 * %B Full month name (January, February etc.)
 * %d Day of the month (01-31)
 * %e Day of the month (1-31)
 * %H Hour in 24-hour clock (00-23)
```

8. LOGOS, WATERMARKS AND STAMPS

```
* %I Hour in 12-hour clock (01-12)
* %j Day of the year (001-366)
* %m Month of the year (01-12)
* %M Minute of the hour (00-59)
* %p "a.m" or "p.m"
* %S Second of the minute (00-61)
* %T Same as %H:%M:%S
* %u Weekday (1-7, 1 = Monday)
* %w Weekday (0-6, 0 = Monday)
* %Y Year (0000-9999)
* %% The % character */

/* The standard fonts */
enum cpdf_font
{
    cpdf_timesRoman, /* Times Roman */
    cpdf_timesBold, /* Times Bold */
    cpdf_timesItalic, /* Times Italic */
    cpdf_timesBoldItalic, /* Times Bold Italic */
    cpdf_helvetica, /* Helvetica */
    cpdf_helveticaBold, /* Helvetica Bold */
    cpdf_helveticaOblique, /* Helvetica Oblique */
    cpdf_helveticaBoldOblique, /* Helvetica Bold Oblique */
    cpdf_courier, /* Courier */
    cpdf_courierBold, /* Courier Bold */
    cpdf_courierOblique, /* Courier Oblique */
    cpdf_courierBoldOblique /* Courier Bold Oblique */
};

/* Justifications for multi line text */
enum cpdf_justification
{
    cpdf_leftJustify, /* Left justify */
    cpdf_CentreJustify, /* Centre justify */
    cpdf_RightJustify /* Right justify */
};

/* Add text */
void cpdf_addText (int, /* If true, don't actually add text but collect metrics. */
                  int, /* Document */
                  int, /* Page Range */
                  const char[], /* The text to add */
                  struct cpdf_position, /* Position to add text at */
                  double, /* Linespacing, 1.0 = normal */
                  int, /* Starting Bates number */
                  enum cpdf_font, /* Font */
                  double, /* Font size in points */
                  double, /* Red component of colour, 0.0 - 1.0 */
                  double, /* Green component of colour, 0.0 - 1.0 */
                  double, /* Blue component of colour, 0.0 - 1.0 */
                  int, /* If true, text is added underneath rather than on top */
                  int, /* If true, position is relative to crop box not media box */
                  int, /* If true, text is outline rather than filled */
                  double, /* Opacity, 1.0 = opaque, 0.0 = wholly transparent */
```

```

        enum cpdf_justification, /* Justification */
        int, /* If true, position is relative to midline of text, not baseline */
        int, /* If true, position is relative to topline of text, not baseline */
        const char[], /* filename that this document was read from (optional) */
        double, /* line width */
        int /* embed fonts */
    );

/* Add text, with most parameters default */
void cpdf_addTextSimple (int, /* Document */
                        int, /* Page range */
                        const char[], /* The text to add */
                        struct cpdf_position, /* Position to add text at */
                        enum cpdf_font, /* font */
                        double); /* font size */

/* To return metrics about the text which would be added. Call cpdf_addText
 * first with the first argument set to false, and the other arguments filled
 * in as appropriate. Now, the metrics have been collected. Call
 * cpdf_addTextHowMany to find out how many lines of text there are. Now, for
 * each line (0...n-1), the functions cpdf_addTextReturn* give the metrics of
 * the text as calculated. */
int cpdf_addTextHowMany (void);
char *cpdf_addTextReturnText (int);
double cpdf_addTextReturnX (int);
double cpdf_addTextReturnY (int);
double cpdf_addTextReturnRotation (int);
double cpdf_addTextReturnBaselineAdjustment (void);

/* cpdf_removeText(pdf, range) will remove any text added by libcpdf from the
 * given pages. */
void cpdf_removeText (int, int);

/* Return the width of a given string in the given font in thousandths of a
 * point. */
int cpdf_textWidth (enum cpdf_font, const char[]);

```

9 Multipage Facilities

```
/* CHAPTER 9. Multipage facilities */

/* Impose a document two up. cpdf_twoUp does so by retaining the existing page
 * size, scaling pages down. cpdf_twoUpStack does so by doubling the page size,
 * to fit two pages on one. */
void cpdf_twoUp (int);
void cpdf_twoUpStack (int);

/* cpdf_padBefore(pdf, range) adds a blank page before each page in the given range */
void cpdf_padBefore (int, int);

/* cpdf_padBefore(pdf, range) adds a blank page before each page in the given range */
void cpdf_padAfter (int, int);

/* cpdf_pageEvery(pdf, n) adds a blank page after every n pages */
void cpdf_padEvery (int, int);

/* cpdf_padMultiple(pdf, n) adds pages at the end to pad the file to a multiple
 * of n pages in length. */
void cpdf_padMultiple (int, int);

/* cpdf_padMultiple(pdf, n) adds pages at the beginning to pad the file to a
 * multiple of n pages in length. */
void cpdf_padMultipleBefore (int, int);
```

10 Annotations

Not supported in libcpdf. Use the command line tools instead.

```
/* CHAPTER 10. Annotations */
```

```
/* Not in the library version */
```

11 Document Information and Metadata

```
/* CHAPTER 11. Document Information and Metadata */

/* cpdf_isLinearized(filename) finds out if a document is linearized as quickly
 * as possible without loading it. */
int cpdf_isLinearized (const char[]);

/* cpdf_vetVersion(pdf) returns the minor version number of a document. */
int cpdf_getVersion (int);

/* cpdf_vetMajorVersion(pdf) returns the minor version number of a document. */
int cpdf_getMajorVersion (int);

/* cpdf_getTitle(pdf) returns the title of a document. */
char *cpdf_getTitle (int);

/* cpdf_getAuthor(pdf) returns the author of a document. */
char *cpdf_getAuthor (int);

/* cpdf_getSubject(pdf) returns the subject of a document. */
char *cpdf_getSubject (int);

/* cpdf_getKeywords(pdf) returns the keywords of a document. */
char *cpdf_getKeywords (int);

/* cpdf_getCreator(pdf) returns the creator of a document. */
char *cpdf_getCreator (int);

/* cpdf_getProducer(pdf) returns the producer of a document. */
char *cpdf_getProducer (int);

/* cpdf_getCreationDate(pdf) returns the creation date of a document. */
char *cpdf_getCreationDate (int);

/* cpdf_getModificationDate(pdf) returns the modification date of a document. */
char *cpdf_getModificationDate (int);

/* cpdf_getTitleXMP(pdf) returns the XMP title of a document. */
char *cpdf_getTitleXMP (int);

/* cpdf_getAuthorXMP(pdf) returns the XMP author of a document. */
char *cpdf_getAuthorXMP (int);
```

11. DOCUMENT INFORMATION AND METADATA

```
/* cpdf_getSubjectXMP(pdf) returns the XMP subject of a document. */
char *cpdf_getSubjectXMP (int);

/* cpdf_getKeywordsXMP(pdf) returns the XMP keywords of a document. */
char *cpdf_getKeywordsXMP (int);

/* cpdf_getCreatorXMP(pdf) returns the XMP creator of a document. */
char *cpdf_getCreatorXMP (int);

/* cpdf_getProducerXMP(pdf) returns the XMP producer of a document. */
char *cpdf_getProducerXMP (int);

/* cpdf_getCreationDateXMP(pdf) returns the XMP creation date of a document. */
char *cpdf_getCreationDateXMP (int);

/* cpdf_getModificationDateXMP(pdf) returns the XMP modification date of a document. */
char *cpdf_getModificationDateXMP (int);

/* cpdf_setTitle(pdf) sets the title of a document. */
void cpdf_setTitle (int, const char[]);

/* cpdf_setAuthor(pdf) sets the author of a document. */
void cpdf_setAuthor (int, const char[]);

/* cpdf_setSubject(pdf) sets the subject of a document. */
void cpdf_setSubject (int, const char[]);

/* cpdf_setKeywords(pdf) sets the keywords of a document. */
void cpdf_setKeywords (int, const char[]);

/* cpdf_setCreator(pdf) sets the creator of a document. */
void cpdf_setCreator (int, const char[]);

/* cpdf_setProducer(pdf) sets the producer of a document. */
void cpdf_setProducer (int, const char[]);

/* cpdf_setCreationDate(pdf) sets the creation date of a document. */
void cpdf_setCreationDate (int, const char[]);

/* cpdf_setModificationDate(pdf) sets the modification date of a document. */
void cpdf_setModificationDate (int, const char[]);

/* cpdf_setTitleXMP(pdf) set the XMP title of a document. */
void cpdf_setTitleXMP (int, const char[]);

/* cpdf_setAuthorXMP(pdf) set the XMP author of a document. */
void cpdf_setAuthorXMP (int, const char[]);

/* cpdf_setSubjectXMP(pdf) set the XMP subject of a document. */
void cpdf_setSubjectXMP (int, const char[]);

/* cpdf_setKeywordsXMP(pdf) set the XMP keywords of a document. */
void cpdf_setKeywordsXMP (int, const char[]);
```

```

/* cpdf_setCreatorXMP(pdf) set the XMP creator of a document. */
void cpdf_setCreatorXMP (int, const char[]);

/* cpdf_setProducerXMP(pdf) set the XMP producer of a document. */
void cpdf_setProducerXMP (int, const char[]);

/* cpdf_setCreationDateXMP(pdf) set the XMP creation date of a document. */
void cpdf_setCreationDateXMP (int, const char[]);

/* cpdf_setModificationDateXMP(pdf) set the XMP modification date of a document. */
void cpdf_setModificationDateXMP (int, const char[]);

/* Dates: Month 1-31, day 1-31, hours (0-23), minutes (0-59), seconds (0-59),
 * hour_offset is the offset from UT in hours (-23 to 23); minute_offset is the
 * offset from UT in minutes (-59 to 59). */

/* cpdf_getDateComponents(datestring, year, month, day, hour, minute, second,
 * hour_offset, minute_offset) returns the components from a PDF date string. */
void cpdf_getDateComponents (const char[], int *, int *, int *, int *, int *,
                             int *, int *, int *);

/* cpdf_dateStringOfComponents(year, month, day, hour, minute, second,
 * hour_offset, minute_offset) builds a PDF date string from individual
 * components. */
char *cpdf_dateStringOfComponents (int, int, int, int, int, int, int, int);

/* cpdf_getPageRotation(pdf, pagenumber) gets the viewing rotation for a given
 * page. */
int cpdf_getPageRotation (int, int);

/* cpdf_hasBox(pdf, pagenumber, boxname) returns true, if that page has the
 * given box. E.g. "/CropBox" */
int cpdf_hasBox (int, int, const char[]);

/* These functions get a box given the document, page range, min x, max x, min y, max y in
 * points. Only succeeds if such a box exists, as checked by cpdf_hasBox */
void cpdf_getMediaBox (int, int, double *, double *, double *, double *);
void cpdf_getCropBox (int, int, double *, double *, double *, double *);
void cpdf_getTrimBox (int, int, double *, double *, double *, double *);
void cpdf_getArtBox (int, int, double *, double *, double *, double *);
void cpdf_getBleedBox (int, int, double *, double *, double *, double *);

/* These functions set a box given the document, page range, min x, max x, min
 * y, max y in points. */
void cpdf_setMediaBox (int, int, double, double, double, double);
void cpdf_setCropBox (int, int, double, double, double, double);
void cpdf_setTrimBox (int, int, double, double, double, double);
void cpdf_setArtBox (int, int, double, double, double, double);
void cpdf_setBleedBox (int, int, double, double, double, double);

/* cpdf_markTrapped(pdf) marks a document as trapped. */
void cpdf_markTrapped (int);

/* cpdf_markUntrapped(pdf) marks a document as untrapped. */

```

11. DOCUMENT INFORMATION AND METADATA

```
void cpdf_markUntrapped (int);

/* cpdf_markTrappedXMP(pdf) marks a document as trapped in XMP metadata. */
void cpdf_markTrappedXMP (int);

/* cpdf_markUntrappedXMP(pdf) marks a document as untrapped in XMP metadata. */
void cpdf_markUntrappedXMP (int);

/* Document Layouts. */
enum cpdf_layout
{
    cpdf_singlePage,
    cpdf_oneColumn,
    cpdf_twoColumnLeft,
    cpdf_twoColumnRight,
    cpdf_twoPageLeft,
    cpdf_twoPageRight
};

/* cpdf_setPageLayout(pdf, layout) sets the page layout for a document. */
void cpdf_setPageLayout (int, enum cpdf_layout);

/* Document page modes. */
enum cpdf_pageMode
{
    cpdf_useNone,
    cpdf_useOutlines,
    cpdf_useThumbs,
    cpdf_useOC,
    cpdf_useAttachments
};

/* cpdf_setPageMode(pdf, mode) sets the page mode for a document. */
void cpdf_setPageMode (int, enum cpdf_pageMode);

/* cpdf_hideToolbar(pdf, flag) sets the hide toolbar flag */
void cpdf_hideToolbar (int, int);

/* cpdf_hideMenubar(pdf, flag) sets the hide menu bar flag */
void cpdf_hideMenubar (int, int);

/* cpdf_hideWindowUi(pdf, flag) sets the hide window UI flag */
void cpdf_hideWindowUi (int, int);

/* cpdf_fitWindow(pdf, flag) sets the fit window flag */
void cpdf_fitWindow (int, int);

/* cpdf_centerWindow(pdf, flag) sets the center window flag */
void cpdf_centerWindow (int, int);

/* cpdf_displayDocTitle(pdf, flag) sets the display doc title flag */
void cpdf_displayDocTitle (int, int);

/* cpdf_openAtPage(pdf, fit, pagenumber) */
```

```

void cpdf_openAtPage (int, int, int);

/* cpdf_setMetadataFromFile(pdf, filename) set the XMP metadata of a document,
 * given a file name. */
void cpdf_setMetadataFromFile (int, const char[]);

/* cpdf_setMetadataFromByteArray(pdf, data, length) set the XMP metadata from
 * an array of bytes. */
void cpdf_setMetadataFromByteArray (int, void *, int);

/* cpdf_getMetadata(pdf, &length) returns the XMP metadata and fills in length. */
void *cpdf_getMetadata (int, int *);

/* cpdf_removeMetadata(pdf) removes the XMP metadata from a document */
void cpdf_removeMetadata (int);

/* cpdf_createMetadata(pdf) builds fresh metadata as best it can from existing
 * metadata in the document. */
void cpdf_createMetadata (int);

/* cpdf_setMetadataDate(pdf, date) sets the metadata date for a PDF. The date
 * is given in PDF date format -- cpdf will convert it to XMP format. The date
 * 'now' means now. */
void cpdf_setMetadataDate (int, const char[]);

/* Styles of page label */
enum cpdf_pageLabelStyle
{
    cpdf_decimalArabic, /* 1,2,3... */
    cpdf_uppercaseRoman, /* I, II, III... */
    cpdf_lowercaseRoman, /* i, ii, iii... */
    cpdf_uppercaseLetters, /* A, B, C... */
    cpdf_lowercaseLetters /* a, b, c... */
};

/* Add a page labels.
 *
 * cpdf_addPageLabels(pdf, style, prefix, offset, range, progress)
 *
 * The prefix is prefix text for each label. The range is the page range the
 * labels apply to. Offset can be used to shift the numbering up or down. */
void cpdf_addPageLabels (int, enum cpdf_pageLabelStyle, const char[], int,
                        int, int);

/* cpdf_removePageLabels(pdf) removes the page labels from the document. */
void cpdf_removePageLabels (int);

/* cpdf_getPageLabelStringForPage(pdf, page number) calculates the full label
 * string for a given page, and returns it */
char *cpdf_getPageLabelStringForPage (int, int);

/* Get page label data. Call cpdf_startGetPageLabels to find out how many there
 * are, then use these serial numbers to get the style, prefix, offset and
 * range. Call cpdf_endGetPageLabels to clean up. */

```

11. DOCUMENT INFORMATION AND METADATA

```
int cpdf_startGetPageLabels (int);  
enum cpdf_pageLabelStyle cpdf_getPageLabelStyle (int);  
char *cpdf_getPageLabelPrefix (int);  
int cpdf_getPageLabelOffset (int);  
int cpdf_getPageLabelRange (int);  
void cpdf_endGetPageLabels ();
```

12 File Attachments

```
/* CHAPTER 12. File Attachments */

/* cpdf_attachFile(filename, pdf) attaches a file to the pdf. It is attached at
 * document level. */
void cpdf_attachFile (const char[], int);

/* cpdf_attachFileToPage(filename, pdf, pagenumber) attaches a file, given its
 * file name, pdf, and the page number to which it should be attached. */
void cpdf_attachFileToPage (const char[], int, int);

/* cpdf_attachFileFromMemory(memory, length, filename, pdf) attaches from
 * memory, just like cpdf_attachFile. */
void cpdf_attachFileFromMemory (void *, int, const char[], int);

/* cpdf_attachFileToPageFromMemory(memory, length, filename, pdf, pagenumber)
 * attaches from memory, just like cpdf_attachFileToPage. */
void cpdf_attachFileToPageFromMemory (void *, int, const char[], int, int);

/* Remove all page- and document-level attachments from a document */
void cpdf_removeAttachedFiles (int);

/* List information about attachments. Call cpdf_startGetAttachments(pdf) first,
 * then cpdf_numberGetAttachments to find out how many there are. Then
 * cpdf_getAttachmentName to return each one 0...(n - 1). Finally, call
 * cpdf_endGetAttachments to clean up. */
void cpdf_startGetAttachments (int);

/* Get the number of attachments. */
int cpdf_numberGetAttachments (void);

/* Get the name of the attachment. */
char *cpdf_getAttachmentName (int);

/* Gets the page number. 0 = document level */
int cpdf_getAttachmentPage (int);

/* cpdf_getAttachmentData(serial number, &length) returns a pointer to the
 * data, and its length */
void *cpdf_getAttachmentData (int, int *);

/* Clean up. */
void cpdf_endGetAttachments (void);
```

13 Images

```
/* CHAPTER 13. Images. */

/* Get image data, including resolution at all points of use. Call
 * cpdf_startGetImageResolution(pdf, min_required_resolution) will begin the
 * process of obtaining data on all image uses below min_required_resolution,
 * returning the total number. So, to return all image uses, specify a very
 * high min_required_resolution. Then, call the other functions giving a serial
 * number 0..<total number> - 1, to retrieve the data. Finally, call
 * cpdf_endGetImageResolution to clean up. */
int cpdf_startGetImageResolution (int, int);
int cpdf_getImageResolutionPageNumber (int);
char *cpdf_getImageResolutionImageName (int);
int cpdf_getImageResolutionXPixels (int);
int cpdf_getImageResolutionYPixels (int);
double cpdf_getImageResolutionXRes (int);
double cpdf_getImageResolutionYRes (int);
void cpdf_endGetImageResolution (void);
```

14 Fonts

```
/* CHAPTER 14. Fonts. */

/* Retrieving font information. First, call cpdf_startGetFontInfo(pdf). Now
 * call cpdf_numberFonts to return the number of fonts. For each font, call one
 * or more of cpdf_getFontPage, cpdf_getFontName, cpdf_getFontType, and
 * cpdf_getFontEncoding giving a serial number 0..<number of fonts> - 1 to return
 * information. Finally, call cpdf_endGetFontInfo to clean up. */
void cpdf_startGetFontInfo (int);
int cpdf_numberFonts (void);
int cpdf_getFontPage (int);
char *cpdf_getFontName (int);
char *cpdf_getFontType (int);
char *cpdf_getFontEncoding (int);
void cpdf_endGetFontInfo (void);

/* cpdf_removeFonts(pdf) removes all font data from a file. */
void cpdf_removeFonts (int);

/* cpdf_copyFont(from, to, range, pagenumber, fontname) copies the given font
 * from the given page in the 'from' PDF to every page in the 'to' PDF. The new
 * font is stored under it's font name. */
void cpdf_copyFont (int, int, int, int, const char[]);
```

15 Miscellaneous

```
/* CHAPTER 15. Miscellaneous */

/* cpdf_draft(pdf, range, boxes) removes images on the given pages, replacing
 * them with crossed boxes if 'boxes' is true */
void cpdf_draft (int, int, int);

/* cpdf_removeAllText(pdf, range) removes all text from the given pages in a
 * given document. */
void cpdf_removeAllText (int, int);

/* cpdf_blackText(pdf, range) blackens all text on the given pages. */
void cpdf_blackText (int, int);

/* cpdf_blackLines(pdf, range) blackens all lines on the given pages. */
void cpdf_blackLines (int, int);

/* cpdf_blackFills(pdf, range) blackens all fills on the given pages. */
void cpdf_blackFills (int, int);

/* cpdf_thinLines(pdf, range, min_thickness) thickens every line less than
 * min_thickness to min_thickness. Thickness given in points. */
void cpdf_thinLines (int, int, double);

/* cpdf_copyId(from, to) copies the /ID from one document to another. */
void cpdf_copyId (int, int);

/* cpdf_removeId(pdf) removes a document's /ID */
void cpdf_removeId (int);

/* cpdf_setVersion(pdf, version) sets the minor version number of a document. */
void cpdf_setVersion (int, int);

/* cpdf_removeDictEntry(pdf, key) removes any dictionary entry with the given
 * key anywhere in the document */
void cpdf_removeDictEntry (int, const char[]);

/* cpdf_removeClipping(pdf, range) removes all clipping from pages in the given
 * range */
void cpdf_removeClipping (int, int);

/* CHAPTER UNDOC */
```

A Dates

Dates in PDF are specified according to the following format:

D : YYYYMMDDHHmmSSOHh' mm'

where:

- YYYY is the year;
- MM is the month;
- DD is the day (01-31);
- HH is the hour (00-23);
- mm is the minute (00-59);
- SS is the second (00-59);
- O is the relationship of local time to Universal Time (UT), denoted by '+', '-' or 'Z';
- Hh is the absolute value of the offset from UT in hours (00-23);
- mm is the absolute value of the offset from UT in minutes (00-59).

A contiguous prefix of the parts above can be used instead, for lower accuracy dates. For example:

D:2011 (2011)

D:20110103 (3rd March 2011)

D:201101031854-08'00' (3rd March 2011, 6:54PM, US Pacific Standard Time)

B Example Program in C

This program loads a file from disk and writes out a document with the original included three times. Note the use of `cpdf_startup`, `cpdf_lastError` and `cpdf_clearError`.

```
#include <stdbool.h>
#include "cpdfplibwrapper.h"

int main (int argc, char ** argv)
{
    /* Initialise cpdf */
    cpdf_startup(argv);

    /* Clear the error state */
    cpdf_clearError();

    /* We will take the input hello.pdf and repeat it three times */
    int mergepdf = cpdf_fromFile("hello.pdf", "");

    /* Check the error state */
    if (cpdf_lastError) return 1;

    /* The array of PDFs to merge */
    int pdfs[] = {mergepdf, mergepdf, mergepdf};

    /* Clear the error state */
    cpdf_clearError();

    /* Merge them */
    int merged = cpdf_mergeSimple(pdfs, 3);

    /* Check the error state */
    if (cpdf_lastError) return 1;

    /* Clear the error state */
    cpdf_clearError();

    /* Write output */
    cpdf_toFile(merged, "merged.pdf", false, false);

    /* Check the error state */
    if (cpdf_lastError) return 1;

    return 0;
}
```


Index

- AND, 4
- annotations
 - copying, 41
 - listing, 41
 - removing, 42
- attachments, 51
 - adding, 51
 - dumping to file, 52
 - listing, 51
 - removing, 52
- bates numbers, 33
- blacken
 - fills, 60
 - lines, 60
 - text, 60
- blank pages
 - inserting, 39
- bookmarks, 25
 - adding, 27
 - listing, 25
 - opening at level, 27
 - removing, 27
- color, 35
- compressing, 23
- control file, 9
- create new PDF, 10
- creator, 5
- crop pages, 18
- date, 32
 - defined, 63
- decompressing, 23
- decryption, 3, 21
- document information, 43
- document outline, 25
- draft, 59
- encryption, 13, 21
- error handling, 9
- file ID, 6
 - copy, 61
 - remove, 61
- flip pages, 18
- font, 34
 - embedding, 10
 - listing, 55
- garbage collection, 61
- hairline removal, 60
- input files, 1
- input range, 2
- linearization, 6
- malformed file, 7
- media box, 18
- merging, 11
- metadata, 43
 - XMP, 46
- object stream, 7
- outline text, 36
- output files, 1
- owner password, 3
- page
 - labels, 48
 - layout, 47
 - mode, 47
 - numbers, 33
 - range, 2
 - size, 16
- password, 3

- presentations, 29
- printer's marks, 19
- producer, 5

- range, 2
- removing text, 32
- reversing, 2
- rotate
 - contents, 18
 - pages, 17

- scale pages, 16
- shift page contents, 17
- splitting, 12
 - on bookmarks, 12
- spot colour, 62
- squeeze, 24
- stamp text, 32
- standard input, 4
- standard output, 4

- text encodings, 10
- time, 32
- trim marks, 19
- two-up, 39

- units, 5
- user password, 3

- version number, 6, 61

- watermarks, 31

- XMP metadata, 46